SAP ABAP table CFB_BINCO_MASTER {CFB Field Catalog for Batch Information Cockpit Master}




CFB_BINCO_MASTER-J_1BTAXLW1_LS = J_1BATL1-TAXLAW
0..N
J_1BATL1
MANDT [CLNT (3)]
TAXLAW [CHAR (3)]
CFB_BINCO_MASTER-TXLW1_KN = J_1BATL1-TAXLAW
0..N
CFB_BINCO_MASTER-J_1BTAXLW2_LS = J_1BATL2-TAXLAW
0..N
J_1BATL2
MANDT [CLNT (3)]
TAXLAW [CHAR (3)]
CFB_BINCO_MASTER-TXLW2_KN = J_1BATL2-TAXLAW
0..N
CFB_BINCO_MASTER-J_1BTAXLW3_LS = J_1BATL3-TAXLAW
0..N
J_1BATL3
MANDT [CLNT (3)]
TAXLAW [CHAR (3)]
CFB_BINCO_MASTER-J_1BTAXLW4_LS = J_1BATL4A-TAXLAW
0..N
J_1BATL4A
MANDT [CLNT (3)]
TAXLAW [CHAR (3)]
CFB_BINCO_MASTER-J_1BTAXLW5_LS = J_1BATL5-TAXLAW
0..N
J_1BATL5
MANDT [CLNT (3)]
TAXLAW [CHAR (3)]
CFB_BINCO_MASTER-CNAE_KN = J_1BTCNAE-J_1BCNAE
0..N
J_1BTCNAE
MANDT [CLNT (3)]
J_1BCNAE [CHAR (7)]
CFB_BINCO_MASTER-COMSIZE_KN = J_1BTCOMSIZE-J_1BCOMSIZE
0..N
J_1BTCOMSIZE
MANDT [CLNT (3)]
J_1BCOMSIZE [CHAR (2)]
CFB_BINCO_MASTER-DECREGPC_KN = J_1BTDECREGPC-J_1BDECREGPC
0..N
J_1BTDECREGPC
MANDT [CLNT (3)]
J_1BDECREGPC [CHAR (2)]
CFB_BINCO_MASTER-ICMSTAXPAY_KN = J_1BTICMSTAXPAY-J_1BICMSTAXPAY
0..N
J_1BTICMSTAXPAY
MANDT [CLNT (3)]
J_1BICMSTAXPAY [CHAR (2)]
CFB_BINCO_MASTER-INDTYP_KN = J_1BTINDTYP-J_1BINDTYP
0..N
J_1BTINDTYP
MANDT [CLNT (3)]
J_1BINDTYP [CHAR (2)]
CFB_BINCO_MASTER-LEGALNAT_KN = J_1BTLEGALNAT-J_1BLEGALNAT
0..N
J_1BTLEGALNAT
MANDT [CLNT (3)]
J_1BLEGALNAT [NUMC (4)]
CFB_BINCO_MASTER-TDT_KN = J_1BTTDT-J_1BTDT
0..N
J_1BTTDT
MANDT [CLNT (3)]
J_1BTDT [CHAR (2)]
CFB_BINCO_MASTER-J_1BTXSDC_LS = J_1BTXSDC-TAXCODE
0..N
J_1BTXSDC
MANDT [CLNT (3)]
TAXCODE [CHAR (2)]
CFB_BINCO_MASTER-XSUBT_KN = J_1BTXSTG-STGRP
0..N
J_1BTXSTG
MANDT [CLNT (3)]
STGRP [CHAR (3)]


CFB_BINCO_MASTER-CLINT_LS = KLAH-CLINT
0..N
KLAH
MANDT [CLNT (3)]
CLINT [NUMC (10)]
CFB_BINCO_MASTER-FISKN_KN = KNA1-KUNNR
CFB_BINCO_MASTER-KNKLI_LK = KNA1-KUNNR
CFB_BINCO_MASTER-KNRZA_KN = KNA1-KUNNR
CFB_BINCO_MASTER-KUNAG_LK = KNA1-KUNNR
CFB_BINCO_MASTER-KUNIV_LK = KNA1-KUNNR
CFB_BINCO_MASTER-KUNNR_LK = KNA1-KUNNR
0..N
KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]
CFB_BINCO_MASTER-LGPLA_LS = LAGP-LGPLA
0..N
LAGP
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
LGTYP [CHAR (3)]
LGPLA [CHAR (10)]
CFB_BINCO_MASTER-LIFNR_KN = LFA1-LIFNR
0..N
LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
CFB_BINCO_MASTER-UECHA_LS = LIPS-POSNR
0..N
LIPS
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
CFB_BINCO_MASTER-/VSO/R_MATPAL_KN = MARA-MATNR
CFB_BINCO_MASTER-EMATN_LS = MARA-MATNR
CFB_BINCO_MASTER-MATNR_LS = MARA-MATNR
CFB_BINCO_MASTER-MATWA_LS = MARA-MATNR
CFB_BINCO_MASTER-TRMTYP_LK = MARA-MATNR
CFB_BINCO_MASTER-VPMAT_LS = MARA-MATNR
0..N
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
CFB_BINCO_MASTER-CHARG_LS = MCHA-CHARG
0..N
MCHA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
CHARG [CHAR (10)]
CFB_BINCO_MASTER-BERID_LS = MDLV-BERID
0..N
MDLV
MANDT [CLNT (3)]
BERID [CHAR (10)]
CFB_BINCO_MASTER-PSOFG_KN = PSO19-PSOFG
0..N
PSO19
MANDT [CLNT (3)]
PSOFG [CHAR (10)]
CFB_BINCO_MASTER-QPLOS_LS = QALS-PRUEFLOS
0..N
QALS
MANDANT [CLNT (3)]
PRUEFLOS [NUMC (12)]
CFB_BINCO_MASTER-SERNR_LS = SNUM-SERNR
0..N
SNUM
MANDT [CLNT (3)]
SERNR [CHAR (8)]
CFB_BINCO_MASTER-MANDT = T000-MANDT
CFB_BINCO_MASTER-MANDT_KN = T000-MANDT
0..N
T000
MANDT [CLNT (3)]
CFB_BINCO_MASTER-MANDT_LK = T000-MANDT
CFB_BINCO_MASTER-MANDT_LS = T000-MANDT
CFB_BINCO_MASTER-LGORT_LS = T001L-LGORT
0..N
T001L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]


CFB_BINCO_MASTER
MANDT [CLNT (3)]
MANDT_LK [CLNT (3)]
VBELN_LK [CHAR (10)]
BZIRK_LK [CHAR (6)]
VSTEL_LK [CHAR (4)]
VKORG_LK [CHAR (4)]
LFART_LK [CHAR (4)]
INCO1_LK [CHAR (3)]
ROUTE_LK [CHAR (6)]
FAKSK_LK [CHAR (2)]
LIFSK_LK [CHAR (2)]
KNFAK_LK [CHAR (2)]
LPRIO_LK [NUMC (2)]
VSBED_LK [CHAR (2)]
KUNNR_LK [CHAR (10)]
KUNAG_LK [CHAR (10)]
KDGRP_LK [CHAR (2)]
GEWEI_LK [UNIT (3)]
VOLEH_LK [UNIT (3)]
GRULG_LK [CHAR (4)]
LSTEL_LK [CHAR (2)]
TRAGR_LK [CHAR (4)]
FKARV_LK [CHAR (4)]
PERFK_LK [CHAR (2)]
ROUTA_LK [CHAR (6)]
KALSM_LK [CHAR (6)]
WAERK_LK [CUKY (5)]
VKBUR_LK [CHAR (4)]
COMMN_LK [CHAR (5)]
STWAE_LK [CUKY (5)]
EXNUM_LK [CHAR (10)]
LGNUM_LK [CHAR (3)]
CFB_BINCO_MASTER-VPWRK_LS = T001W-WERKS
CFB_BINCO_MASTER-WERKS_KN = T001W-WERKS
CFB_BINCO_MASTER-WERKS_LK = T001W-WERKS
CFB_BINCO_MASTER-WERKS_LS = T001W-WERKS
CFB_BINCO_MASTER-SPRAS_KN = T002-SPRAS
CFB_BINCO_MASTER-LAND1_KN = T005-LAND1
CFB_BINCO_MASTER-COUNC_KN = T005E-COUNC
CFB_BINCO_MASTER-CITYC_KN = T005G-CITYC
CFB_BINCO_MASTER-REGIO_KN = T005S-BLAND
CFB_BINCO_MASTER-/VSO/R_PAL_UL_KN = T006-MSEHI
CFB_BINCO_MASTER-GEWEI_LK = T006-MSEHI
CFB_BINCO_MASTER-GEWEI_LS = T006-MSEHI
CFB_BINCO_MASTER-KCGEWEI_LS = T006-MSEHI
CFB_BINCO_MASTER-KCVOLEH_LS = T006-MSEHI
CFB_BINCO_MASTER-KMEIN_LS = T006-MSEHI
CFB_BINCO_MASTER-MEINS_LS = T006-MSEHI
CFB_BINCO_MASTER-PRBME_LS = T006-MSEHI
CFB_BINCO_MASTER-VOLEH_LK = T006-MSEHI
CFB_BINCO_MASTER-VOLEH_LS = T006-MSEHI
CFB_BINCO_MASTER-VRKME_LS = T006-MSEHI
CFB_BINCO_MASTER-PERIV_KN = T009-PERIV
CFB_BINCO_MASTER-KKBER_LK = T014-KKBER
CFB_BINCO_MASTER-BRSCH_KN = T016-BRSCH
CFB_BINCO_MASTER-MATKL_LS = T023-MATKL
CFB_BINCO_MASTER-SBGRP_LK = T024B-SBGRP
CFB_BINCO_MASTER-KTOCD_KN = T077D-KTOKD
CFB_BINCO_MASTER-KTOKD_KN = T077D-KTOKD
CFB_BINCO_MASTER-MTART_LS = T134-MTART
CFB_BINCO_MASTER-SOBKZ_LS = T148-SOBKZ
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
T002
SPRAS [LANG (1)]
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
T005E
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
COUNC [CHAR (3)]
T005G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
CITYC [CHAR (4)]
T005S
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
T009
MANDT [CLNT (3)]
PERIV [CHAR (2)]
T014
MANDT [CLNT (3)]
KKBER [CHAR (4)]
T016
MANDT [CLNT (3)]
BRSCH [CHAR (4)]
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
T024B
MANDT [CLNT (3)]
SBGRP [CHAR (3)]
KKBER [CHAR (4)]
T077D
MANDT [CLNT (3)]
KTOKD [CHAR (4)]
T134
MANDT [CLNT (3)]
MTART [CHAR (4)]
T148
MANDT [CLNT (3)]
SOBKZ [CHAR (1)]
0..N
{0,1}
1

VKOIV_LK [CHAR (4)]
VTWIV_LK [CHAR (2)]
SPAIV_LK [CHAR (2)]
FKAIV_LK [CHAR (4)]
PIOIV_LK [CHAR (2)]
KUNIV_LK [CHAR (10)]
KKBER_LK [CHAR (4)]
KNKLI_LK [CHAR (10)]
SBGRP_LK [CHAR (3)]
CTLPC_LK [CHAR (3)]
CMWAE_LK [CUKY (5)]
TRATY_LK [CHAR (4)]
TRSPG_LK [CHAR (2)]
TPSID_LK [CHAR (5)]
TERNR_LK [CHAR (12)]
KALSM_CH_LK [CHAR (6)]
KALSP_LK [CHAR (6)]
AULWE_LK [CHAR (10)]
WERKS_LK [CHAR (4)]
LCNUM_LK [CHAR (10)]
ABSSC_LK [CHAR (6)]
LGTOR_LK [CHAR (3)]
LGBZO_LK [CHAR (10)]
AKWAE_LK [CUKY (5)]
PROLI_LK [CHAR (3)]
VSART_LK [CHAR (2)]
TRMTYP_LK [CHAR (18)]
SDABW_LK [CHAR (4)]
MANDT_LS [CLNT (3)]
VBELN_LS [CHAR (10)]
POSNR_LS [NUMC (6)]
PSTYV_LS [CHAR (4)]
MATNR_LS [CHAR (18)]
MATWA_LS [CHAR (18)]
MATKL_LS [CHAR (9)]
WERKS_LS [CHAR (4)]
LGORT_LS [CHAR (4)]
CHARG_LS [CHAR (10)]
PRODH_LS [CHAR (18)]
MEINS_LS [UNIT (3)]
VRKME_LS [UNIT (3)]
GEWEI_LS [UNIT (3)]
VOLEH_LS [UNIT (3)]
FAKSP_LS [CHAR (2)]
VBELV_LS [CHAR (10)]
POSNV_LS [NUMC (6)]
VGSYS_LS [CHAR (10)]
VGBEL_LS [CHAR (10)]
VGPOS_LS [NUMC (6)]
UEPOS_LS [NUMC (6)]
LADGR_LS [CHAR (4)]
TRAGR_LS [CHAR (4)]
LGNUM_LS [CHAR (3)]
LGTYP_LS [CHAR (3)]
LGPLA_LS [CHAR (10)]
BWART_LS [CHAR (3)]
BWLVS_LS [NUMC (3)]
MTART_LS [CHAR (4)]
BWTAR_LS [CHAR (10)]
MTVFP_LS [CHAR (2)]
GSBER_LS [CHAR (4)]
VKBUR_LS [CHAR (4)]
VKGRP_LS [CHAR (3)]
VTWEG_LS [CHAR (2)]
SPART_LS [CHAR (2)]
SOBKZ_LS [CHAR (1)]



KVGR1_LS [CHAR (3)]
KVGR2_LS [CHAR (3)]
KVGR3_LS [CHAR (3)]
KVGR4_LS [CHAR (3)]
KVGR5_LS [CHAR (3)]
MVGR1_LS [CHAR (3)]
MVGR2_LS [CHAR (3)]
MVGR3_LS [CHAR (3)]
MVGR4_LS [CHAR (3)]
MVGR5_LS [CHAR (3)]
KOSTL_LS [CHAR (10)]
KOKRS_LS [CHAR (4)]
AUFNR_LS [CHAR (12)]
VPMAT_LS [CHAR (18)]
VPWRK_LS [CHAR (4)]
PRBME_LS [UNIT (3)]
KNTTP_LS [CHAR (1)]
BEDAR_LF_LS [CHAR (3)]
UECHA_LS [NUMC (6)]
SERAIL_LS [CHAR (4)]
KCGEWEI_LS [UNIT (3)]
KCVOLEH_LS [UNIT (3)]
SERNR_LS [CHAR (8)]
ABRLI_LS [NUMC (4)]
ABRVW_LS [CHAR (3)]
QPLOS_LS [NUMC (12)]
MAGRV_LS [CHAR (4)]
ABTNR_LS [CHAR (4)]
AKTNR_LS [CHAR (10)]
CLINT_LS [NUMC (10)]
ABELN_LS [CHAR (10)]
ABELP_LS [NUMC (5)]
KMEIN_LS [UNIT (3)]
MFRGR_LS [CHAR (8)]
ABFOR_LS [CHAR (2)]
WKTNR_LS [CHAR (10)]
WKTPS_LS [NUMC (6)]
J_1BCFOP_LS [CHAR (10)]
J_1BTAXLW1_LS [CHAR (3)]
J_1BTAXLW2_LS [CHAR (3)]
J_1BTXSDC_LS [CHAR (2)]
PROFL_LS [CHAR (3)]
RULES_LS [CHAR (4)]
EMATN_LS [CHAR (18)]
LGBZO_LS [CHAR (10)]
BERID_LS [CHAR (10)]
J_1BTAXLW4_LS [CHAR (3)]
J_1BTAXLW5_LS [CHAR (3)]
J_1BTAXLW3_LS [CHAR (3)]
MANDT_KN [CLNT (3)]
LAND1_KN [CHAR (3)]
REGIO_KN [CHAR (3)]
AUFSD_KN [CHAR (2)]
BRSCH_KN [CHAR (4)]
FAKSD_KN [CHAR (2)]



FISKN_KN [CHAR (10)]
KNAZK_KN [CHAR (2)]
KNRZA_KN [CHAR (10)]
KTOKD_KN [CHAR (4)]
KUKLA_KN [CHAR (2)]
LIFNR_KN [CHAR (10)]
LIFSD_KN [CHAR (2)]
NIELS_KN [CHAR (2)]
COUNC_KN [CHAR (3)]
CITYC_KN [CHAR (4)]
SPRAS_KN [LANG (1)]
LZONE_KN [CHAR (10)]
VBUND_KN [CHAR (6)]
GFORM_KN [CHAR (2)]
BRAN1_KN [CHAR (10)]
BRAN2_KN [CHAR (10)]
BRAN3_KN [CHAR (10)]
BRAN4_KN [CHAR (10)]
BRAN5_KN [CHAR (10)]
EKONT_KN [CHAR (10)]
UWAER_KN [CUKY (5)]
KATR1_KN [CHAR (2)]
KATR2_KN [CHAR (2)]
KATR3_KN [CHAR (2)]
KATR4_KN [CHAR (2)]
KATR5_KN [CHAR (2)]
KATR6_KN [CHAR (3)]
KATR7_KN [CHAR (3)]
KATR8_KN [CHAR (3)]
KATR9_KN [CHAR (3)]
KATR10_KN [CHAR (3)]
TXJCD_KN [CHAR (15)]
PERIV_KN [CHAR (2)]
ABRVW_KN [CHAR (3)]
KTOCD_KN [CHAR (4)]
WERKS_KN [CHAR (4)]
ETIKG_KN [CHAR (10)]
KDKG1_KN [CHAR (2)]
KDKG2_KN [CHAR (2)]
KDKG3_KN [CHAR (2)]
KDKG4_KN [CHAR (2)]
KDKG5_KN [CHAR (2)]
FITYP_KN [CHAR (2)]
STCDT_KN [CHAR (2)]
XSUBT_KN [CHAR (3)]
TXLW1_KN [CHAR (3)]
TXLW2_KN [CHAR (3)]
J_1KFTBUS_KN [CHAR (30)]
J_1KFTIND_KN [CHAR (30)]
CNAE_KN [CHAR (7)]
LEGALNAT_KN [NUMC (4)]
ICMSTAXPAY_KN [CHAR (2)]
INDTYP_KN [CHAR (2)]
TDT_KN [CHAR (2)]
COMSIZE_KN [CHAR (2)]
DECREGPC_KN [CHAR (2)]
_VSO_R_PAL_UL_KN [UNIT (3)]
_VSO_R_MATPAL_KN [CHAR (18)]
_VSO_R_DPOINT_KN [CHAR (10)]
ALC_KN [CHAR (8)]
PMT_OFFICE_KN [CHAR (5)]
PSOFG_KN [CHAR (10)]

CFB_BINCO_MASTER-KOKRS_LS = TKA01-KOKRS
{0,1} 0..N
TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

CFB_BINCO_MASTER-KUKLA_KN = TKUKL-KUKLA
{0,1} 0..N
TKUKL
MANDT [CLNT (3)]
KUKLA [CHAR (2)]

CFB_BINCO_MASTER-LADGR_LS = TLGR-LADGR
1 0..N
TLGR
MANDT [CLNT (3)]
LADGR [CHAR (4)]

CFB_BINCO_MASTER-MFRGR_LS = TMFG-MFRGR
{0,1} 0..N
TMFG
MANDT [CLNT (3)]
MFRGR [CHAR (8)]

CFB_BINCO_MASTER-MTVFP_LS = TMVF-MTVFP
{0,1} 0..N
TMVF
MANDT [CLNT (3)]
MTVFP [CHAR (2)]

CFB_BINCO_MASTER-NIELS_KN = TNLS-NIELS
{0,1} 0..N
TNLS
MANDT [CLNT (3)]
NIELS [CHAR (2)]

CFB_BINCO_MASTER-LPRIO_LK = TPRIO-LPRIO
{0,1} 0..N
TPRIO
MANDT [CLNT (3)]
LPRIO [NUMC (2)]

CFB_BINCO_MASTER-COMMN_LK = TQCOM-COMMN
{0,1} 0..N

CFB_BINCO_MASTER-TPSID_LK = TQCOM-COMMN
1 0..N
TQCOM
COMMN [CHAR (5)]

CFB_BINCO_MASTER-ABTNR_LS = TSAB-ABTNR
{0,1} 0..N
TSAB
MANDT [CLNT (3)]
ABTNR [CHAR (4)]

CFB_BINCO_MASTER-SPAIV_LK = TSPA-SPART
{0,1}

CFB_BINCO_MASTER-SPART_LS = TSPA-SPART
{0,1} 0..N
TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]

CFB_BINCO_MASTER-TRAGR_LK = TTGR-TRAGR
{0,1} 0..N

CFB_BINCO_MASTER-TRAGR_LS = TTGR-TRAGR
0..N
TTGR
MANDT [CLNT (3)]
TRAGR [CHAR (4)]

CFB_BINCO_MASTER-TRSPG_LK = TTSG-TRSPG
{0,1} 0..N
TTSG
MANDT [CLNT (3)]
TRSPG [CHAR (2)]

CFB_BINCO_MASTER-TXJCD_KN = TTXJ-TXJCD
{0,1} 0..N
TTXJ
MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (15)]

CFB_BINCO_MASTER-AUFSD_KN = TVAST-AUFSP
{0,1} 0..N
TVAST
MANDT [CLNT (3)]
SPRAS [LANG (1)]
AUFSP [CHAR (2)]

CFB_BINCO_MASTER-VKBUR_LK = TVBUR-VKBUR
{0,1}

CFB_BINCO_MASTER-VKBUR_LS = TVBUR-VKBUR
{0,1} 0..N
TVBUR
MANDT [CLNT (3)]
VKBUR [CHAR (4)]

CFB_BINCO_MASTER-MAGRV_LS = TVEGR-MAGRV
{0,1} 0..N


CFB_BINCO_MASTER-FKAIV_LK = TVFK-FKART
0..N
TVEGR
MANDT [CLNT (3)]
MAGRV [CHAR (4)]
CFB_BINCO_MASTER-FKARV_LK = TVFK-FKART
0..N
TVFK
MANDT [CLNT (3)]
FKART [CHAR (4)]
CFB_BINCO_MASTER-FAKSD_KN = TVFS-FAKSP
0..N
CFB_BINCO_MASTER-FAKSK_LK = TVFS-FAKSP
0..N
TVFS
MANDT [CLNT (3)]
FAKSP [CHAR (2)]
CFB_BINCO_MASTER-FAKSP_LS = TVFS-FAKSP
0..N
CFB_BINCO_MASTER-GFORM_KN = TVGF-GFORM
0..N
TVGF
MANDT [CLNT (3)]
GFORM [CHAR (2)]
CFB_BINCO_MASTER-KATR10_KN = TVK0-KATR10
0..N
TVK0
MANDT [CLNT (3)]
KATR10 [CHAR (3)]
CFB_BINCO_MASTER-KATR1_KN = TVK1-KATR1
0..N
TVK1
MANDT [CLNT (3)]
KATR1 [CHAR (2)]
CFB_BINCO_MASTER-KATR2_KN = TVK2-KATR2
0..N
TVK2
MANDT [CLNT (3)]
KATR2 [CHAR (2)]
CFB_BINCO_MASTER-KATR3_KN = TVK3-KATR3
0..N
TVK3
MANDT [CLNT (3)]
KATR3 [CHAR (2)]
CFB_BINCO_MASTER-KATR4_KN = TVK4-KATR4
0..N
TVK4
MANDT [CLNT (3)]
KATR4 [CHAR (2)]
CFB_BINCO_MASTER-KATR5_KN = TVK5-KATR5
0..N
TVK5
MANDT [CLNT (3)]
KATR5 [CHAR (2)]
CFB_BINCO_MASTER-KATR6_KN = TVK6-KATR6
0..N
TVK6
MANDT [CLNT (3)]
KATR6 [CHAR (3)]
CFB_BINCO_MASTER-KATR7_KN = TVK7-KATR7
0..N
TVK7
MANDT [CLNT (3)]
KATR7 [CHAR (3)]
CFB_BINCO_MASTER-KATR8_KN = TVK8-KATR8
0..N
TVK8
MANDT [CLNT (3)]
KATR8 [CHAR (3)]
CFB_BINCO_MASTER-KATR9_KN = TVK9-KATR9
0..N
TVK9
MANDT [CLNT (3)]
KATR9 [CHAR (3)]
CFB_BINCO_MASTER-KDKG1_KN = TVKGG-KDKGR
0..N
CFB_BINCO_MASTER-KDKG2_KN = TVKGG-KDKGR
0..N
CFB_BINCO_MASTER-KDKG3_KN = TVKGG-KDKGR
0..N
CFB_BINCO_MASTER-KDKG4_KN = TVKGG-KDKGR
0..N
CFB_BINCO_MASTER-KDKG5_KN = TVKGG-KDKGR
0..N
TVKGG
MANDT [CLNT (3)]
KDKGR [CHAR (2)]
CFB_BINCO_MASTER-VKGRP_LS = TVKGR-VKGRP
0..N
TVKGR
MANDT [CLNT (3)]
VKGRP [CHAR (3)]
CFB_BINCO_MASTER-VKOIV_LK = TVKO-VKORG

CFB_BINCO_MASTER-VKORG_LK = TVKO-VKORG
0..N
TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]
0..N
CFB_BINCO_MASTER-LSTEL_LK = TVLA-LSTEL
TVLA
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
LSTEL [CHAR (2)]
0..N
CFB_BINCO_MASTER-GRULG_LK = TVLG-GRULG
TVLG
MANDT [CLNT (3)]
GRULG [CHAR (4)]
0..N
CFB_BINCO_MASTER-LFART_LK = TVLK-LFART
TVLK
MANDT [CLNT (3)]
LFART [CHAR (4)]
0..N
CFB_BINCO_MASTER-LIFSD_KN = TVLS-LIFSP
CFB_BINCO_MASTER-LIFSK_LK = TVLS-LIFSP
TVLS
MANDT [CLNT (3)]
LIFSP [CHAR (2)]
0..N
0..N
CFB_BINCO_MASTER-ABRVW_KN = TVLV-ABRVW
CFB_BINCO_MASTER-ABRVW_LS = TVLV-ABRVW
TVLV
MANDT [CLNT (3)]
ABRVW [CHAR (3)]
0..N
0..N
CFB_BINCO_MASTER-MVGR1_LS = TVM1-MVGR1
TVM1
MANDT [CLNT (3)]
MVGR1 [CHAR (3)]
0..N
CFB_BINCO_MASTER-MVGR2_LS = TVM2-MVGR2
TVM2
MANDT [CLNT (3)]
MVGR2 [CHAR (3)]
0..N
CFB_BINCO_MASTER-MVGR3_LS = TVM3-MVGR3
TVM3
MANDT [CLNT (3)]
MVGR3 [CHAR (3)]
0..N
CFB_BINCO_MASTER-MVGR4_LS = TVM4-MVGR4
TVM4
MANDT [CLNT (3)]
MVGR4 [CHAR (3)]
0..N
CFB_BINCO_MASTER-MVGR5_LS = TVM5-MVGR5
TVM5
MANDT [CLNT (3)]
MVGR5 [CHAR (3)]
0..N
CFB_BINCO_MASTER-PSTYV_LS = TVPT-PSTYV
TVPT
MANDT [CLNT (3)]
PSTYV [CHAR (4)]
0..N
CFB_BINCO_MASTER-ROUTA_LK = TVRO-ROUTE
CFB_BINCO_MASTER-ROUTE_LK = TVRO-ROUTE
TVRO
MANDT [CLNT (3)]
ROUTE [CHAR (6)]
0..N
0..N
CFB_BINCO_MASTER-SDABW_LK = TVSAK-SDABW
TVSAK
MANDT [CLNT (3)]
SDABW [CHAR (4)]
0..N
CFB_BINCO_MASTER-VSBED_LK = TVSB-VSBED
TVSB
MANDT [CLNT (3)]
VSBED [CHAR (2)]
0..N
CFB_BINCO_MASTER-VSTEL_LK = TVST-VSTEL
TVST
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
0..N
CFB_BINCO_MASTER-VTWEG_LS = TVTW-VTWEG


CFB_BINCO_MASTER-VTWIV_LK = TVTW-VTWEG
0..N
0..N
TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]
CFB_BINCO_MASTER-TRATY_LK = TVTY-TRATY
0..N
TVTY
MANDT [CLNT (3)]
TRATY [CHAR (4)]
CFB_BINCO_MASTER-KVGR1_LS = TVV1-KVGR1
0..N
TVV1
MANDT [CLNT (3)]
KVGR1 [CHAR (3)]
CFB_BINCO_MASTER-KVGR2_LS = TVV2-KVGR2
0..N
TVV2
MANDT [CLNT (3)]
KVGR2 [CHAR (3)]
CFB_BINCO_MASTER-KVGR3_LS = TVV3-KVGR3
0..N
TVV3
MANDT [CLNT (3)]
KVGR3 [CHAR (3)]
CFB_BINCO_MASTER-KVGR4_LS = TVV4-KVGR4
0..N
TVV4
MANDT [CLNT (3)]
KVGR4 [CHAR (3)]
CFB_BINCO_MASTER-KVGR5_LS = TVV5-KVGR5
0..N
TVV5
MANDT [CLNT (3)]
KVGR5 [CHAR (3)]
CFB_BINCO_MASTER-ETIKG_KN = TWEK-KUNGR
0..N
TWEK
MANDT [CLNT (3)]
KUNGR [CHAR (10)]
CFB_BINCO_MASTER-LZONE_KN = TZONE-ZONE1
0..N
TZONE
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
ZONE1 [CHAR (10)]
CFB_BINCO_MASTER-AULWE_LK = VALW-AULWE
0..N
VALW
MANDT [CLNT (3)]
AULWE [CHAR (10)]
CFB_BINCO_MASTER-ABRLI_LS = VBLB-ABRLI
CFB_BINCO_MASTER-EKONT_KN = VBUK-VBELN
CFB_BINCO_MASTER-VBELN_LK = VBUK-VBELN
CFB_BINCO_MASTER-VBELN_LS = VBUK-VBELN
CFB_BINCO_MASTER-VBELV_LS = VBUK-VBELN
CFB_BINCO_MASTER-VGBEL_LS = VBUK-VBELN
CFB_BINCO_MASTER-WKTNR_LS = VBUK-VBELN
0..N
VBLB
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
ABRLI [NUMC (4)]
ABART [CHAR (1)]
CFB_BINCO_MASTER-POSNR_LS = VBUP-POSNR
{0,1}
0..N
{0,1}
0..N
VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]
CFB_BINCO_MASTER-POSNV_LS = VBUP-POSNR
CFB_BINCO_MASTER-UEPOS_LS = VBUP-POSNR
0..N
{0,1}
VBUP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
CFB_BINCO_MASTER-VGPOS_LS = VBUP-POSNR
0..N
0..N
CFB_BINCO_MASTER-WKTPS_LS = VBUP-POSNR
0..N
CFB_BINCO_MASTER-AKTNR_LS = WAKH-AKTNR
0..N
WAKH
MANDT [CLNT (3)]
AKTNR [CHAR (10)]