SAP ABAP table COWB_S_OPERATION {Display Structure for Order Operations}


COWB_S_OPERATION-/CUM/CUGUID = /CUM/AFCU-CUGUID
_CUM_AFCU
MANDT [CLNT (3)]
CUGUID [RAW (16)]
COWB_S_OPERATION-AENNR = AENR-AENNR
AENR
MANDT [CLNT (3)]
AENNR [CHAR (12)]
COWB_S_OPERATION-APLZL = AFVC-APLZL
AFVC
MANDT [CLNT (3)]
AUFPL [NUMC (10)]
APLZL [NUMC (8)]
COWB_S_OPERATION-PRCTR = CEPC-PRCTR
CEPC
MANDT [CLNT (3)]
PRCTR [CHAR (10)]
DATBI [DATS (8)]
KOKRS [CHAR (4)]
COWB_S_OPERATION-ARBID = CRID-OBJID
COWB_S_OPERATION-ARBII = CRID-OBJID
CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]
COWB_S_OPERATION-SAKTO = CSKA-KSTAR
CSKA
MANDT [CLNT (3)]
KTOPL [CHAR (4)]
KSTAR [CHAR (10)]
COWB_S_OPERATION-ANFKO = CSKS-KOSTL
CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]
COWB_S_OPERATION-LAR01 = CSLA-LSTAR
COWB_S_OPERATION-LAR02 = CSLA-LSTAR
COWB_S_OPERATION-LAR03 = CSLA-LSTAR
COWB_S_OPERATION-LAR04 = CSLA-LSTAR
COWB_S_OPERATION-LAR05 = CSLA-LSTAR
COWB_S_OPERATION-LAR06 = CSLA-LSTAR
COWB_S_OPERATION-LARNT = CSLA-LSTAR
CSLA
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
LSTAR [CHAR (6)]
DATBI [DATS (8)]
COWB_S_OPERATION-BNFPO = EBAN-BNFPO
EBAN
MANDT [CLNT (3)]
BANFN [CHAR (10)]
BNFPO [NUMC (5)]
COWB_S_OPERATION-INFNR = EINA-INFNR
EINA
MANDT [CLNT (3)]
INFNR [CHAR (10)]
COWB_S_OPERATION-EBELN = EKKO-EBELN
COWB_S_OPERATION-KONNR = EKKO-EBELN
EKKO
MANDT [CLNT (3)]
EBELN [CHAR (10)]
COWB_S_OPERATION-EBELP = EKPO-EBELP
COWB_S_OPERATION-KTPNR = EKPO-EBELP
EKPO
MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
COWB_S_OPERATION-FERC_IND = FERC_C7-IND
FERC_C7
MANDT [CLNT (3)]
IND [CHAR (4)]
COWB_S_OPERATION-LIFNR = LFA1-LIFNR
LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
COWB_S_OPERATION-ISTRU = MARA-MATNR
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
COWB_S_OPERATION-OBJNR = ONR00-OBJNR
ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]
COWB_S_OPERATION-PROJN = PRPS-PSPNR
PRPS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]
COWB_S_OPERATION-MANDT = T000-MANDT
T000
MANDT [CLNT (3)]
COWB_S_OPERATION-BUKRS = T001-BUKRS
T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
COWB_S_OPERATION-WERKI = T001W-WERKS
COWB_S_OPERATION-WERKS = T001W-WERKS
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
COWB_S_OPERATION-TXTSP = T002-SPRAS
T002
SPRAS [LANG (1)]
COWB_S_OPERATION-ARBEH = T006-MSEHI
COWB_S_OPERATION-CONF_UNIT = T006-MSEHI
COWB_S_OPERATION-DAUME = T006-MSEHI
COWB_S_OPERATION-DAUNE = T006-MSEHI
COWB_S_OPERATION-EHOFFB = T006-MSEHI
COWB_S_OPERATION-EHOFFE = T006-MSEHI
COWB_S_OPERATION-EWDME = T006-MSEHI
COWB_S_OPERATION-EWDNE = T006-MSEHI
COWB_S_OPERATION-LOSME = T006-MSEHI
COWB_S_OPERATION-MEINH = T006-MSEHI
COWB_S_OPERATION-PDAE = T006-MSEHI
COWB_S_OPERATION-USE04 = T006-MSEHI
COWB_S_OPERATION-USE05 = T006-MSEHI
COWB_S_OPERATION-VGE01 = T006-MSEHI
COWB_S_OPERATION-VGE02 = T006-MSEHI
COWB_S_OPERATION-VGE03 = T006-MSEHI
COWB_S_OPERATION-VGE04 = T006-MSEHI
COWB_S_OPERATION-VGE05 = T006-MSEHI
COWB_S_OPERATION-VGE06 = T006-MSEHI
COWB_S_OPERATION-ZEIER = T006-MSEHI
COWB_S_OPERATION-ZEILM = T006-MSEHI
COWB_S_OPERATION-ZEILP = T006-MSEHI
COWB_S_OPERATION-ZEIMB = T006-MSEHI
COWB_S_OPERATION-ZEIMU = T006-MSEHI
COWB_S_OPERATION-ZEITM = T006-MSEHI
COWB_S_OPERATION-ZEITN = T006-MSEHI
COWB_S_OPERATION-ZEIWM = T006-MSEHI
COWB_S_OPERATION-ZEIWN = T006-MSEHI
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
COWB_S_OPERATION-MATKL = T023-MATKL
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
COWB_S_OPERATION-EKGRP = T024-EKGRP
T024
MANDT [CLNT (3)]
EKGRP [CHAR (3)]
T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]
T357M
MANDT [CLNT (3)]
ANLZU [CHAR (1)]
T421
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LOGRP [CHAR (3)]
T423
MANDT [CLNT (3)]
WERKS [CHAR (4)]
QUALF [CHAR (2)]
T425
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RFGRP [CHAR (10)]
RFSCH [CHAR (10)]
T426
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RFGRP [CHAR (10)]
0..N
COWB_S_OPERATION
MANDT [CLNT (3)]
APLZL [NUMC (8)]
PLNTY [CHAR (1)]
STEUS [CHAR (4)]
ARBID [NUMC (8)]
PDEST [CHAR (4)]
WERKS [CHAR (4)]
KTSCH [CHAR (7)]
TXTSP [LANG (1)]
VPLTY [CHAR (1)]
VGWTS [CHAR (4)]
LAR01 [CHAR (6)]
LAR02 [CHAR (6)]
LAR03 [CHAR (6)]
LAR04 [CHAR (6)]
LAR05 [CHAR (6)]
LAR06 [CHAR (6)]
ZERMA [CHAR (5)]
QUALF [CHAR (2)]
RFGRP [CHAR (10)]
RFSCH [CHAR (10)]
RASCH [CHAR (2)]
LOGRP [CHAR (3)]
RSTRA [CHAR (2)]
LIFNR [CHAR (10)]
SAKTO [CHAR (10)]
WAERS [CUKY (5)]
INFNR [CHAR (10)]
EKORG [CHAR (4)]
EKGRP [CHAR (3)]
MATKL [CHAR (9)]
MLSTN [CHAR (5)]
BUKRS [CHAR (4)]
ANFKO [CHAR (10)]
ANFKOKRS [CHAR (4)]
LARNT [CHAR (6)]
PROJN [NUMC (8)]
OBJNR [CHAR (22)]
BNFPO [NUMC (5)]
SELKZ [CHAR (1)]
KALID [CHAR (2)]
ANLZU [CHAR (1)]
ISTRU [CHAR (18)]
VERTL [CHAR (1)]
NPRIO [CHAR (1)]
PHSEQ [CHAR (2)]
OTYPE [CHAR (2)]
QLKAPAR [CHAR (3)]
TXJCD [CHAR (15)]
GSBER [CHAR (4)]
PRCTR [CHAR (10)]
AENNR [CHAR (12)]
ARBII [NUMC (8)]
WERKI [CHAR (4)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
OWAER [CUKY (5)]
QPART [CHAR (8)]
RFPNT [CHAR (20)]
FUNC_AREA [CHAR (16)]
RFIPPNT [CHAR (20)]
_CUM_CUGUID [RAW (16)]
MEINH [UNIT (3)]
ZEIER [UNIT (3)]
VGE01 [UNIT (3)]
VGE02 [UNIT (3)]
VGE03 [UNIT (3)]


VGE04 [UNIT (3)]
VGE05 [UNIT (3)]
VGE06 [UNIT (3)]
ZEIMU [UNIT (3)]
ZEIMB [UNIT (3)]
ZEILM [UNIT (3)]
ZEILP [UNIT (3)]
ZEIWN [UNIT (3)]
ZEIWM [UNIT (3)]
ZEITN [UNIT (3)]
ZEITM [UNIT (3)]
DAUNE [UNIT (3)]
DAUME [UNIT (3)]
ARBEH [UNIT (3)]
EWDNE [UNIT (3)]
EWDME [UNIT (3)]
BZOFFB [CHAR (2)]
EHOFFB [UNIT (3)]
BZOFFE [CHAR (2)]
EHOFFE [UNIT (3)]
PDAE [UNIT (3)]
KNOTE [CHAR (10)]
VSTZW [CHAR (4)]
VSTGA [CHAR (4)]
SLWID [CHAR (7)]
USE04 [UNIT (3)]
USE05 [UNIT (3)]
USE06 [CUKY (5)]
USE07 [CUKY (5)]
VNAME [CHAR (6)]
RECID [CHAR (2)]
ETYPE [CHAR (3)]
JV_JIBCL [CHAR (3)]
JV_JIBSA [CHAR (5)]
FERC_IND [CHAR (4)]
FLGAT [CHAR (1)]
LOSME [UNIT (3)]
KONNR [CHAR (10)]
KTPNR [NUMC (5)]
CONF_UNIT [UNIT (3)]
COWB_S_OPERATION-EKORG = T024E-EKORG
COWB_S_OPERATION-ANLZU = T357M-ANLZU
COWB_S_OPERATION-LOGRP = T421-LOGRP
COWB_S_OPERATION-QUALF = T423-QUALF
COWB_S_OPERATION-RFSCH = T425-RFSCH
COWB_S_OPERATION-RFGRP = T426-RFGRP
COWB_S_OPERATION-RASCH = T428-RASCH
COWB_S_OPERATION-ZERMA = T429-ZERMA
COWB_S_OPERATION-STEUS = T430-STEUS
COWB_S_OPERATION-MLSTN = T433-MLSTN
COWB_S_OPERATION-KTSCH = T435-VLSCH
COWB_S_OPERATION-RSTRA = T499Q-RSTRA
COWB_S_OPERATION-OTYPE = T778O-OTYPE
COWB_S_OPERATION-JV_JIBCL = T8J6A-CLASS
COWB_S_OPERATION-JV_JIBSA = T8J6C-SUBCLASS
COWB_S_OPERATION-ETYPE = T8JG-ETYPE
COWB_S_OPERATION-RECID = T8JJ-RECID
COWB_S_OPERATION-VNAME = T8JV-VNAME
COWB_S_OPERATION-VGWTS = TC21-VGWTS
COWB_S_OPERATION-QLKAPAR = TC26-KAPAR
COWB_S_OPERATION-VERTL = TC29-VERTL
COWB_S_OPERATION-PHSEQ = TC52-PHSEQ
COWB_S_OPERATION-PLNTY = TCA01-PLNTY
COWB_S_OPERATION-VPLTY = TCA01-PLNTY
COWB_S_OPERATION-FLGAT = TCA07-FLGAT
COWB_S_OPERATION-BZOFFB = TCA54-BZOFF
COWB_S_OPERATION-BZOFFE = TCA54-BZOFF
COWB_S_OPERATION-SELKZ = TCK08-SELKZ
COWB_S_OPERATION-SLWID = TCN00-SLWID
COWB_S_OPERATION-NPRIO = TCN07-NPRIO
COWB_S_OPERATION-RFPNT = TCNRFP-RFPNT
COWB_S_OPERATION-RFIPPNT = TCNRPIP-RFPNT
COWB_S_OPERATION-OWAER = TCURC-WAERS
COWB_S_OPERATION-USE06 = TCURC-WAERS
COWB_S_OPERATION-USE07 = TCURC-WAERS
COWB_S_OPERATION-WAERS = TCURC-WAERS
COWB_S_OPERATION-KALID = TFACD-IDENT
COWB_S_OPERATION-FUNC_AREA = TFKB-FKBER
COWB_S_OPERATION-GSBER = TGSB-GSBER
COWB_S_OPERATION-ANFKOKRS = TKA01-KOKRS
COWB_S_OPERATION-QPART = TQ30-ART
COWB_S_OPERATION-PDEST = TSP03-PADEST
COWB_S_OPERATION-TXJCD = TTXJ-TXJCD
COWB_S_OPERATION-KNOTE = TVKN-KNOTE
COWB_S_OPERATION-VSTGA = TVTG-VSTGA
COWB_S_OPERATION-VSTZW = TVTZ-VSTZW
0..N
1
T428
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RASCH [CHAR (2)]
T429
MANDT [CLNT (3)]
WERKS [CHAR (4)]
ZERMA [CHAR (5)]
T430
MANDT [CLNT (3)]
PLNAW [CHAR (1)]
STEUS [CHAR (4)]
T433
MANDT [CLNT (3)]
MLSTN [CHAR (5)]
T435
MANDT [CLNT (3)]
VLSCH [CHAR (7)]
T499Q
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RSTRA [CHAR (2)]
T778O
MANDT [CLNT (3)]
OTYPE [CHAR (2)]
T8J6A
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
CLASS [CHAR (3)]
T8J6C
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
CLASS [CHAR (3)]
SUBCLASS [CHAR (5)]
T8JG
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VNAME [CHAR (6)]
ETYPE [CHAR (3)]
FDATE [NUMC (8)]
T8JJ
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
RECID [CHAR (2)]
T8JV
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VNAME [CHAR (6)]
TC21
MANDT [CLNT (3)]
VGWTS [CHAR (4)]
TC26
MANDT [CLNT (3)]
KAPAR [CHAR (3)]
TC29
MANDT [CLNT (3)]
VERTL [CHAR (8)]
TC52
MANDT [CLNT (3)]
WERKS [CHAR (4)]
PHSEQ [CHAR (2)]
TCA01
MANDT [CLNT (3)]
PLNTY [CHAR (1)]
TCA07
FLGAT [CHAR (1)]
TCA54
BZOFF [CHAR (2)]
TCK08
MANDT [CLNT (3)]
SELKZ [CHAR (1)]
TCN00
MANDT [CLNT (3)]
SLWID [CHAR (7)]
TCN07
MANDT [CLNT (3)]
NPRIO [CHAR (1)]
TCNRFP
MANDT [CLNT (3)]
RFPNT [CHAR (20)]
TCNRPIP
MANDT [CLNT (3)]
RFPNT [CHAR (20)]
TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]
TFACD
IDENT [CHAR (2)]
TFKB
MANDT [CLNT (3)]
FKBER [CHAR (16)]
TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]
TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
TQ30
MANDT [CLNT (3)]
ART [CHAR (8)]
TSP03
PADEST [CHAR (4)]
TTXJ
MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (15)]
TVKN
MANDT [CLNT (3)]
KNOTE [CHAR (10)]
TVTG
MANDT [CLNT (3)]
VSTGA [CHAR (4)]
TVTZ
MANDT [CLNT (3)]
VSTZW [CHAR (4)]