SAP ABAP table CSIM_ST_HEADER_FOKUS {Structure for the iPPE Explosion for the Configuration Simu.}




CSIM_ST_HEADER_FOKUS-STOFFA = MGEF-STOFF
CSIM_ST_HEADER_FOKUS-UMRSLC = OIB01-UMRSL
CSIM_ST_HEADER_FOKUS-UOMGRC = OIB06-UOMGR
CSIM_ST_HEADER_FOKUS-ENTRYIDF = PPEFILTEXPLPAR-EXPL_GUID
CSIM_ST_HEADER_FOKUS-VSPVBC = PVBE-PRVBE
CSIM_ST_HEADER_FOKUS-RDPRFC = RDPR-RDPRF
CSIM_ST_HEADER_FOKUS-PS_SMARTFORMA = STXFADM-FORMNAME
CSIM_ST_HEADER_FOKUS-MANDTA = T000-MANDT
CSIM_ST_HEADER_FOKUS-MANDTC = T000-MANDT
CSIM_ST_HEADER_FOKUS-MANDTF = T000-MANDT
CSIM_ST_HEADER_FOKUS-LGFSBC = T001L-LGORT
CSIM_ST_HEADER_FOKUS-LGPROC = T001L-LGORT
CSIM_ST_HEADER_FOKUS-VRBWKC = T001W-WERKS
CSIM_ST_HEADER_FOKUS-WERKSC = T001W-WERKS
CSIM_ST_HEADER_FOKUS-HERKLA = T005-LAND1
CSIM_ST_HEADER_FOKUS-HERKLC = T005-LAND1
CSIM_ST_HEADER_FOKUS-HERKRC = T005S-BLAND
CSIM_ST_HEADER_FOKUS-AUSMEC = T006-MSEHI
CSIM_ST_HEADER_FOKUS-BSTMEA = T006-MSEHI
CSIM_ST_HEADER_FOKUS-ERGEIA = T006-MSEHI
CSIM_ST_HEADER_FOKUS-ERVOEA = T006-MSEHI
CSIM_ST_HEADER_FOKUS-EXPMEC = T006-MSEHI
CSIM_ST_HEADER_FOKUS-FRTMEC = T006-MSEHI
CSIM_ST_HEADER_FOKUS-GEWEIA = T006-MSEHI
CSIM_ST_HEADER_FOKUS-INHMEA = T006-MSEHI
CSIM_ST_HEADER_FOKUS-LZEIHC = T006-MSEHI
0..N
OIB06
MANDT [CLNT (3)]
UOMGR [CHAR (3)]
PPEFILTEXPLPAR
MANDT [CLNT (3)]
EXPL_GUID [RAW (16)]
PVBE
MANDT [CLNT (3)]
WERKS [CHAR (4)]
PRVBE [CHAR (10)]
RDPR
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RDPRF [CHAR (4)]
RDZAE [NUMC (6)]
STXFADM
FORMNAME [CHAR (30)]
T000
MANDT [CLNT (3)]
T001L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
T005S
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
T009
MANDT [CLNT (3)]
PERIV [CHAR (2)]
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
T024
MANDT [CLNT (3)]
EKGRP [CHAR (3)]

CSIM_ST_HEADER_FOKUS
MANDTF [CLNT (3)]
PFTYPEF [CHAR (8)]
ENTRYIDF [RAW (16)]
MANDTA [CLNT (3)]
MTARTA [CHAR (4)]
MBRSHA [CHAR (1)]
MATKLA [CHAR (9)]
MEINSA [UNIT (3)]
BSTMEA [UNIT (3)]
WRKSTA [CHAR (48)]
LABORA [CHAR (3)]
EKWSLA [CHAR (4)]
GEWEIA [UNIT (3)]
VOLEHA [UNIT (3)]
BEHVOA [CHAR (2)]
RAUBEA [CHAR (2)]
TEMPBA [CHAR (2)]
TRAGRA [CHAR (4)]
STOFFA [CHAR (18)]
SPARTA [CHAR (2)]
KUNNRA [CHAR (10)]
BWVORA [CHAR (1)]
BWSCLA [CHAR (1)]
SAISOA [CHAR (4)]
ETIARA [CHAR (2)]
ETIFOA [CHAR (2)]
NUMTPA [CHAR (2)]
MEABMA [UNIT (3)]
PRDHAA [CHAR (18)]
ERGEIA [UNIT (3)]
ERVOEA [UNIT (3)]
CSIM_ST_HEADER_FOKUS-MAXDIM_UOMA = T006-MSEHI
CSIM_ST_HEADER_FOKUS-MEABMA = T006-MSEHI
CSIM_ST_HEADER_FOKUS-MEINSA = T006-MSEHI
CSIM_ST_HEADER_FOKUS-QQTIMEUOMA = T006-MSEHI
CSIM_ST_HEADER_FOKUS-VOLEHA = T006-MSEHI
CSIM_ST_HEADER_FOKUS-PERIVC = T009-PERIV
CSIM_ST_HEADER_FOKUS-MATKLA = T023-MATKL
CSIM_ST_HEADER_FOKUS-EKGRPC = T024-EKGRP
CSIM_ST_HEADER_FOKUS-DISPOC = T024D-DISPO
CSIM_ST_HEADER_FOKUS-FEVORC = T024F-FEVOR
CSIM_ST_HEADER_FOKUS-LABORA = T024L-LABOR
CSIM_ST_HEADER_FOKUS-MTARTA = T134-MTART
CSIM_ST_HEADER_FOKUS-MBRSHA = T137-MBRSH
CSIM_ST_HEADER_FOKUS-MMSTAC = T141-MMSTA
CSIM_ST_HEADER_FOKUS-MSTAEA = T141-MMSTA
CSIM_ST_HEADER_FOKUS-RAUBEA = T142-RAUBE
CSIM_ST_HEADER_FOKUS-TEMPBA = T143-TEMPB
CSIM_ST_HEADER_FOKUS-BEHVOA = T144-BEHVO
CSIM_ST_HEADER_FOKUS-BWTTYC = T149C-BWTTY
CSIM_ST_HEADER_FOKUS-ABCINC = T159C-ABCIN
CSIM_ST_HEADER_FOKUS-PRDHAA = T179-PRODH
CSIM_ST_HEADER_FOKUS-KOSCHA = T190S-KOSCH
CSIM_ST_HEADER_FOKUS-RBNRMA = T352B-RBNR
CSIM_ST_HEADER_FOKUS-MEDIUMA = T372M-MEDIU
{0,1}
0..N
T024D
MANDT [CLNT (3)]
WERKS [CHAR (4)]
DISPO [CHAR (3)]
T024F
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FEVOR [CHAR (3)]
T024L
MANDT [CLNT (3)]
LABOR [CHAR (3)]
T134
MANDT [CLNT (3)]
MTART [CHAR (4)]
T137
MANDT [CLNT (3)]
MBRSH [CHAR (1)]
T141
MANDT [CLNT (3)]
MMSTA [CHAR (2)]
T142
MANDT [CLNT (3)]
RAUBE [CHAR (2)]
T143
MANDT [CLNT (3)]
TEMPB [CHAR (2)]
T144
MANDT [CLNT (3)]
BEHVO [CHAR (2)]
T149C
MANDT [CLNT (3)]
BWTTY [CHAR (1)]
T159C
MANDT [CLNT (3)]
WERKS [CHAR (4)]
ABCIN [CHAR (1)]
T179
MANDT [CLNT (3)]
PRODH [CHAR (18)]
T190S
MANDT [CLNT (3)]
KOSCH [CHAR (18)]
T352B
MANDT [CLNT (3)]
RBNR [CHAR (9)]
T372M
MANDT [CLNT (3)]
MEDIU [CHAR (6)]

VHARTA [CHAR (4)]
MAGRVA [CHAR (4)]
PLGTPA [CHAR (2)]
EXTWGA [CHAR (18)]
SATNRA [CHAR (18)]
PMATAA [CHAR (18)]
MSTAEA [CHAR (2)]
MSTAVA [CHAR (2)]
TAKLVA [CHAR (1)]
RBNRMA [CHAR (9)]
INHMEA [UNIT (3)]
ETIAGA [CHAR (18)]
KOSCHA [CHAR (18)]
MFRNRA [CHAR (10)]
BMATNA [CHAR (18)]
MPROFA [CHAR (4)]
SAITYA [CHAR (2)]
PROFLA [CHAR (3)]
COMPLA [NUMC (2)]
MTPOS_MARAA [CHAR (4)]
GENNRA [CHAR (18)]
RMATPA [CHAR (18)]
HUTYP_DFLTA [CHAR (4)]
WHSTCA [CHAR (2)]
WHMATGRA [CHAR (4)]
HNDLCODEA [CHAR (4)]
HUTYPA [CHAR (4)]
MAXDIM_UOMA [UNIT (3)]
HERKLA [CHAR (3)]
MFRGRA [CHAR (8)]
QQTIMEUOMA [UNIT (3)]
QGRPA [CHAR (4)]
SERIALA [CHAR (4)]
PS_SMARTFORMA [CHAR (30)]
LOGUNITA [UNIT (3)]
CWQPROCA [CHAR (2)]
CWQTOLGRA [CHAR (9)]
ADPROFA [CHAR (3)]
MEDIUMA [CHAR (6)]
COMMODITYA [CHAR (18)]
ANPA [NUMC (9)]
_BEV1_LULDEGRPA [CHAR (3)]
_DSD_SL_TOLTYPA [CHAR (4)]
_DSD_SV_CNT_GRPA [CHAR (10)]
_DSD_VC_GROUPA [CHAR (6)]
PACKCODEA [CHAR (10)]
DG_PACK_STATUSA [CHAR (10)]
BSTATA [CHAR (2)]
BRAND_IDA [CHAR (4)]
FIBER_CODE1A [CHAR (3)]
FIBER_CODE2A [CHAR (3)]
FIBER_CODE3A [CHAR (3)]
FIBER_CODE4A [CHAR (3)]
FIBER_CODE5A [CHAR (3)]
FASHGRDA [CHAR (4)]
MANDTC [CLNT (3)]
MATNRC [CHAR (18)]
WERKSC [CHAR (4)]
BWTTYC [CHAR (1)]
MMSTAC [CHAR (2)]
MAABCC [CHAR (1)]
EKGRPC [CHAR (3)]
AUSMEC [UNIT (3)]
DISPRC [CHAR (4)]
DISMMC [CHAR (2)]
DISPOC [CHAR (3)]
DISLSC [CHAR (2)]

CSIM_ST_HEADER_FOKUS-SERNPC = T377P-SERAIL
0..N
0..N

T377P
MANDT [CLNT (3)]
SERAIL [CHAR (4)]

CSIM_ST_HEADER_FOKUS-EKWSLA = T405-EKWSL
{0,1}
0..N

T405
MANDT [CLNT (3)]
EKWSL [CHAR (4)]

CSIM_ST_HEADER_FOKUS-STLANC = T416-STLAN
{0,1}
0..N

T416
MANDT [CLNT (3)]
STLAN [CHAR (1)]

CSIM_ST_HEADER_FOKUS-EPRIOC = T434G-EPRIO
{0,1}
0..N

T434G
MANDT [CLNT (3)]
WERKS [CHAR (4)]
EPRIO [CHAR (4)]

CSIM_ST_HEADER_FOKUS-FHORIC = T436A-FHORI
0..N
0..N

T436A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FHORI [CHAR (3)]

CSIM_ST_HEADER_FOKUS-SFEPRC = T437S-SFPRO
1
0..N

T437S
MANDT [CLNT (3)]
SFPRO [CHAR (4)]

CSIM_ST_HEADER_FOKUS-DISMMC = T438A-DISMM
{0,1}
0..N

T438A
MANDT [CLNT (3)]
DISMM [CHAR (2)]

CSIM_ST_HEADER_FOKUS-DISGRC = T438M-MTART
1
0..N

T438M
MANDT [CLNT (3)]
WERKS [CHAR (4)]
MTART [CHAR (4)]

CSIM_ST_HEADER_FOKUS-RWPROC = T438R-RWPRO
{0,1}
0..N

T438R
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RWPRO [CHAR (3)]

CSIM_ST_HEADER_FOKUS-SHPROC = T438V-SHPRO
{0,1}
0..N

T438V
MANDT [CLNT (3)]
WERKS [CHAR (4)]
SHPRO [CHAR (3)]

CSIM_ST_HEADER_FOKUS-DISLSC = T439A-DISLS
0..N
0..N

T439A
MANDT [CLNT (3)]
DISLS [CHAR (2)]

CSIM_ST_HEADER_FOKUS-LFRHYC = T439G-MRPPP
{0,1}
0..N

CSIM_ST_HEADER_FOKUS-MRPPPC = T439G-MRPPP
{0,1}
0..N
0..N

T439G
MANDT [CLNT (3)]
WERKS [CHAR (4)]
MRPPP [CHAR (3)]

CSIM_ST_HEADER_FOKUS-LAGPRC = T439L-LAGPR
{0,1}
0..N

T439L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LAGPR [CHAR (1)]

CSIM_ST_HEADER_FOKUS-AUFTLC = T439P-AUFTL
{0,1}
0..N

T439P
MANDT [CLNT (3)]
WERKS [CHAR (4)]
PERKZ [CHAR (1)]
AUFTL [CHAR (1)]

CSIM_ST_HEADER_FOKUS-SOBSKC = T460A-SOBSL
{0,1}
0..N

SOBSLC [CHAR (2)]
LAGPRC [CHAR (1)]
NFMATC [CHAR (18)]
FHORIC [CHAR (3)]
FEVORC [CHAR (3)]
LZEIHC [UNIT (3)]
SSQSSC [CHAR (8)]
LADGRC [CHAR (4)]
USEQUC [CHAR (1)]
AUFTLC [CHAR (1)]
PLVARC [CHAR (2)]
OTYPEC [CHAR (2)]
MTVFPC [CHAR (2)]
PERIVC [CHAR (2)]
BWSCLC [CHAR (1)]
STAWNC [CHAR (17)]
HERKLC [CHAR (3)]
HERKRC [CHAR (3)]
EXPMEC [UNIT (3)]
MTVERC [CHAR (4)]
MRPPPC [CHAR (3)]
STLANC [CHAR (1)]
SOBSKC [CHAR (2)]
FRTMEC [UNIT (3)]
LGPROC [CHAR (4)]
DISGRC [CHAR (4)]
QZGTPC [CHAR (4)]
RWPROC [CHAR (3)]
ABCINC [CHAR (1)]
AWSLSC [CHAR (6)]
SERNPC [CHAR (4)]
STDPDC [CHAR (18)]
SFEPRC [CHAR (4)]
QSSYSC [CHAR (4)]
LFRHYC [CHAR (3)]
RDPRFC [CHAR (4)]
VRBMTC [CHAR (18)]
VRBWKC [CHAR (4)]
SERVGC [CHAR (1)]
STRGRC [CHAR (2)]
LGFSBC [CHAR (4)]
EPRIOC [CHAR (4)]
QMATAC [CHAR (6)]
PLNTYC [CHAR (1)]
UOMGRC [CHAR (3)]
UMRSLC [CHAR (4)]
SFCPFC [CHAR (6)]
MDACHC [CHAR (2)]
MEGRUC [CHAR (4)]
MFRGRC [CHAR (8)]
LOGGRC [CHAR (4)]
FPRFMC [CHAR (3)]
MOWNRC [CHAR (12)]
MOGRUC [CHAR (6)]
CASNRC [CHAR (15)]
GPNUMC [CHAR (9)]
STEUCC [CHAR (16)]
VSPVBC [CHAR (10)]
COMPLC [NUMC (2)]
CONVTC [CHAR (2)]
SHPROC [CHAR (3)]
OCMPFC [CHAR (6)]
UCMATC [CHAR (18)]

{0,1} CSIM_ST_HEADER_FOKUS-SOBSLC = T460A-SOBSL 0..N

T460A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
SOBSL [CHAR (2)]

0..N CSIM_ST_HEADER_FOKUS-STRGRC = T461P-STRGR 0..N

T461P
MANDT [CLNT (3)]
STRGR [CHAR (2)]

0..N CSIM_ST_HEADER_FOKUS-MDACHC = T46AC-MDACH 0..N

T46AC
MANDT [CLNT (3)]
MDACH [CHAR (2)]
ACCFM [CHAR (4)]
ACCTO [CHAR (4)]

{0,1} CSIM_ST_HEADER_FOKUS-STAWNC = T604-STAWN 0..N

T604
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
STAWN [CHAR (17)]

0..N CSIM_ST_HEADER_FOKUS-STEUCC = T604F-STEUC 0..N

T604F
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
STEUC [CHAR (16)]

0..N CSIM_ST_HEADER_FOKUS-GPNUMC = T609G-GPNUM 0..N

T609G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
GPNUM [CHAR (9)]

0..N CSIM_ST_HEADER_FOKUS-CASNRC = T610C-CASNR 0..N

T610C
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
CASNR [CHAR (15)]

0..N CSIM_ST_HEADER_FOKUS-MOGRUC = T618G-MOGRU 0..N

T618G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
MOGRU [CHAR (6)]

0..N CSIM_ST_HEADER_FOKUS-MOWNRC = T618M-MOWNR 0..N

T618M
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
MOWNR [CHAR (12)]

0..N CSIM_ST_HEADER_FOKUS-FASHGRDA = T6WFG-FASHGRD 0..N

T6WFG
MANDT [CLNT (3)]
FASHGRD [CHAR (4)]

0..N CSIM_ST_HEADER_FOKUS-BWVORA = T6WP1-BWVOR 0..N

T6WP1
MANDT [CLNT (3)]
BWVOR [CHAR (1)]

{0,1} CSIM_ST_HEADER_FOKUS-ETIARA = T6WP3-ETIAR 0..N

T6WP3
MANDT [CLNT (3)]
ETIAR [CHAR (2)]

{0,1} CSIM_ST_HEADER_FOKUS-ETIFOA = T6WP4-ETIFO 0..N

T6WP4
MANDT [CLNT (3)]
ETIFO [CHAR (2)]

0..N


_VSO_R_PKGRPC [CHAR (18)]
IUID_TYPEC [CHAR (10)]
CONS_PROCGC [CHAR (1)]
REF_SCHEMAC [CHAR (2)]
{0,1}
CSIM_ST_HEADER_FOKUS-SAITYA = T6WSA-SAITY
T6WSA
MANDT [CLNT (3)]
SAITY [CHAR (2)]
0..N
CSIM_ST_HEADER_FOKUS-SAISOA = T6WSP-SAISO
T6WSP
MANDT [CLNT (3)]
SAISO [CHAR (4)]
0..N
CSIM_ST_HEADER_FOKUS-OTYPEC = T778O-OTYPE
T778O
MANDT [CLNT (3)]
OTYPE [CHAR (2)]
0..N
CSIM_ST_HEADER_FOKUS-PLVARC = T778P-PLVAR
T778P
MANDT [CLNT (3)]
PLVAR [CHAR (2)]
0..N
CSIM_ST_HEADER_FOKUS-ADPROFA = TAPROF-ADPROF
TAPROF
MANDT [CLNT (3)]
ADPROF [CHAR (3)]
0..N
CSIM_ST_HEADER_FOKUS-COMMODITYA = TBAC_PHYSCOMM-COMMODITY
TBAC_PHYSCOMM
CLIENT [CLNT (3)]
COMMODITY [CHAR (18)]
0..N
CSIM_ST_HEADER_FOKUS-PLNTYC = TCA01-PLNTY
TCA01
MANDT [CLNT (3)]
PLNTY [CHAR (1)]
0..N
CSIM_ST_HEADER_FOKUS-SFCPFC = TCO43-CO_PRODPRF
TCO43
MANDT [CLNT (3)]
WERKS [CHAR (4)]
CO_PRODPRF [CHAR (6)]
0..N
CSIM_ST_HEADER_FOKUS-OCMPFC = TCO48-GPROFILE
TCO48
MANDT [CLNT (3)]
GPROFILE [CHAR (6)]
0..N
CSIM_ST_HEADER_FOKUS-COMPLA = TCSCP_COMP_LVL-COMP_LEVEL
TCSCP_COMP_LVL
MANDT [CLNT (3)]
COMP_LEVEL [NUMC (2)]
0..N
CSIM_ST_HEADER_FOKUS-COMPLC = TCSCP_COMP_LVL-COMP_LEVEL
0..N
CSIM_ST_HEADER_FOKUS-CONVTC = TCSCP_CONV_TYPE-CONV_TYPE
TCSCP_CONV_TYPE
MANDT [CLNT (3)]
CONV_TYPE [CHAR (2)]
0..N
CSIM_ST_HEADER_FOKUS-CWQPROCA = TCWQPROC-CWQPROC
TCWQPROC
MANDT [CLNT (3)]
CWQPROC [CHAR (2)]
1..N
CSIM_ST_HEADER_FOKUS-CWQTOLGRA = TCWQTOLGR-CWQTOLGR
TCWQTOLGR
MANDT [CLNT (3)]
CWQTOLGR [CHAR (9)]
1..N
CSIM_ST_HEADER_FOKUS-DG_PACK_STATUSA = TDG101-DG_PACK_STATUS
TDG101
MANDT [CLNT (3)]
DG_PACK_STATUS [CHAR (10)]
0..N
CSIM_ST_HEADER_FOKUS-PROFLA = TDG41-PROFL
TDG41
MANDT [CLNT (3)]
PROFL [CHAR (3)]
0..N
CSIM_ST_HEADER_FOKUS-HNDLCODEA = THNDLCD-HNDLCODE
THNDLCD
MANDT [CLNT (3)]
HNDLCODE [CHAR (4)]
0..N
CSIM_ST_HEADER_FOKUS-HUTYPA = THUTYP-HUTYP


CSIM_ST_HEADER_FOKUS-HUTYP_DFLTA = THUTYP-HUTYP
0..N
0..N
THUTYP
MANDT [CLNT (3)]
HUTYP [CHAR (4)]
CSIM_ST_HEADER_FOKUS-IUID_TYPEC = TIUID_TYPE-IUID_TYPE
0..N
TIUID_TYPE
IUID_TYPE [CHAR (10)]
CSIM_ST_HEADER_FOKUS-AWSLSC = TKV01-AWSLS
0..N
TKV01
MANDT [CLNT (3)]
AWOBA [CHAR (2)]
AWSLS [CHAR (6)]
CSIM_ST_HEADER_FOKUS-LADGRC = TLGR-LADGR
0..N
TLGR
MANDT [CLNT (3)]
LADGR [CHAR (4)]
CSIM_ST_HEADER_FOKUS-LOGGRC = TLOG-LOGGR
0..N
TLOG
MANDT [CLNT (3)]
LOGGR [CHAR (4)]
CSIM_ST_HEADER_FOKUS-MAABCC = TMABC-MAABC
0..N
TMABC
MANDT [CLNT (3)]
MAABC [CHAR (1)]
CSIM_ST_HEADER_FOKUS-BWSCLA = TMBW1-BWSCL
CSIM_ST_HEADER_FOKUS-BWSCLC = TMBW1-BWSCL
0..N
0..N
TMBW1
MANDT [CLNT (3)]
BWSCL [CHAR (1)]
CSIM_ST_HEADER_FOKUS-MFRGRA = TMFG-MFRGR
CSIM_ST_HEADER_FOKUS-MFRGRC = TMFG-MFRGR
0..N
0..N
TMFG
MANDT [CLNT (3)]
MFRGR [CHAR (8)]
CSIM_ST_HEADER_FOKUS-FPRFMC = TMFPF-FPRFM
0..N
TMFPF
MANDT [CLNT (3)]
FPRFM [CHAR (3)]
CSIM_ST_HEADER_FOKUS-MPROFA = TMPPF-MPROF
0..N
TMPPF
MANDT [CLNT (3)]
MPROF [CHAR (4)]
CSIM_ST_HEADER_FOKUS-USEQUC = TMQ2-USEQU
0..N
TMQ2
MANDT [CLNT (3)]
USEQU [CHAR (1)]
CSIM_ST_HEADER_FOKUS-MTVFPC = TMVF-MTVFP
0..N
TMVF
MANDT [CLNT (3)]
MTVFP [CHAR (2)]
CSIM_ST_HEADER_FOKUS-NUMTPA = TNTP-NUMTP
0..N
TNTP
MANDT [CLNT (3)]
NUMTP [CHAR (2)]
CSIM_ST_HEADER_FOKUS-MTPOS_MARAA = TPTM-MTPOS
0..N
TPTM
MANDT [CLNT (3)]
MTPOS [CHAR (4)]
CSIM_ST_HEADER_FOKUS-QMATAC = TQ01B-QMATAUTH
0..N
TQ01B
MANDT [CLNT (3)]
QMATAUTH [CHAR (6)]


CSIM_ST_HEADER_FOKUS-QSSYSC = TQ02-QSSYS
0..N
TQ02
MANDT [CLNT (3)]
QSSYS [CHAR (4)]
CSIM_ST_HEADER_FOKUS-QZGTPC = TQ05-ZGTYP
0..N
TQ05
MANDT [CLNT (3)]
ZGTYP [CHAR (4)]
CSIM_ST_HEADER_FOKUS-SSQSSC = TQ08-QM_PUR
0..N
TQ08
MANDT [CLNT (3)]
QM_PUR [CHAR (8)]
CSIM_ST_HEADER_FOKUS-QGRPA = TQGRP-QGRP
0..N
TQGRP
MANDT [CLNT (3)]
QGRP [CHAR (4)]
CSIM_ST_HEADER_FOKUS-SERIALA = TSERIAL-SERIAL
0..N
TSERIAL
MANDT [CLNT (3)]
SERIAL [CHAR (4)]
CSIM_ST_HEADER_FOKUS-TAKLVA = TSKM-TAXKM
0..N
TSKM
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKM [CHAR (1)]
CSIM_ST_HEADER_FOKUS-SPARTA = TSPA-SPART
0..N
TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]
CSIM_ST_HEADER_FOKUS-TRAGRA = TTGR-TRAGR
0..N
TTGR
MANDT [CLNT (3)]
TRAGR [CHAR (4)]
CSIM_ST_HEADER_FOKUS-MAGRVA = TVEGR-MAGRV
0..N
TVEGR
MANDT [CLNT (3)]
MAGRV [CHAR (4)]
CSIM_ST_HEADER_FOKUS-MTVERC = TVFM-MTVER
0..N
TVFM
MANDT [CLNT (3)]
MTVER [CHAR (4)]
CSIM_ST_HEADER_FOKUS-MSTAVA = TVMS-VMSTA
0..N
TVMS
MANDT [CLNT (3)]
VMSTA [CHAR (2)]
CSIM_ST_HEADER_FOKUS-VHARTA = TVTY-TRATY
0..N
TVTY
MANDT [CLNT (3)]
TRATY [CHAR (4)]
CSIM_ST_HEADER_FOKUS-ETIAGA = TWEA-ARTGR
0..N
TWEA
MANDT [CLNT (3)]
ARTGR [CHAR (18)]
CSIM_ST_HEADER_FOKUS-EXTWGA = TWEW-EXTWG
0..N
TWEW
MANDT [CLNT (3)]
EXTWG [CHAR (18)]
CSIM_ST_HEADER_FOKUS-WHMATGRA = TWHMATGR-WHMATGR
0..N
TWHMATGR
MANDT [CLNT (3)]
WHMATGR [CHAR (4)]
CSIM_ST_HEADER_FOKUS-WHSTCA = TWHSTC-WHSTC
0..N
TWHSTC
MANDT [CLNT (3)]
WHSTC [CHAR (2)]


CSIM_ST_HEADER_FOKUS-MEGRUC = TWMEG-MEGRU
TWMEG
MANDT [CLNT (3)]
MEGRU [CHAR (4)]
MEINS [UNIT (3)]
0..N
CSIM_ST_HEADER_FOKUS-PLGTPA = TWPT-PLGTP
TWPT
MANDT [CLNT (3)]
PLGTP [CHAR (2)]
0..N
CSIM_ST_HEADER_FOKUS-SERVGC = TWSG-SERVG
TWSG
MANDT [CLNT (3)]
SERVG [CHAR (1)]
0..N
CSIM_ST_HEADER_FOKUS-WRKSTA = TWSPR-WRKST
TWSPR
MANDT [CLNT (3)]
WRKST [CHAR (48)]
0..N
CSIM_ST_HEADER_FOKUS-KUNNRA = V_KNA1WETT-KUNNR
V_KNA1WETT
MANDT [CLNT (3)]
KUNNR [CHAR (10)]
0..N
CSIM_ST_HEADER_FOKUS-BSTATA = WRFMATBSTAT-BSTAT
WRFMATBSTAT
MANDT [CLNT (3)]
BSTAT [CHAR (2)]
0..N
CSIM_ST_HEADER_FOKUS-CONS_PROCGC = WRFT_CONS_PROCG-WRF_CONS_PROCG
WRFT_CONS_PROCG
MANDT [CLNT (3)]
WRF_CONS_PROCG [CHAR (1)]
0..N
CSIM_ST_HEADER_FOKUS-BRAND_IDA = WRF_BRANDS-BRAND_ID
WRF_BRANDS
MANDT [CLNT (3)]
BRAND_ID [CHAR (4)]
0..N
CSIM_ST_HEADER_FOKUS-FIBER_CODE1A = WRF_FIBER_CODES-FIBER_CODE
CSIM_ST_HEADER_FOKUS-FIBER_CODE2A = WRF_FIBER_CODES-FIBER_CODE
CSIM_ST_HEADER_FOKUS-FIBER_CODE3A = WRF_FIBER_CODES-FIBER_CODE
CSIM_ST_HEADER_FOKUS-FIBER_CODE4A = WRF_FIBER_CODES-FIBER_CODE
CSIM_ST_HEADER_FOKUS-FIBER_CODE5A = WRF_FIBER_CODES-FIBER_CODE
0..N
0..N
0..N
0..N
0..N
WRF_FIBER_CODES
MANDT [CLNT (3)]
FIBER_CODE [CHAR (3)]
CSIM_ST_HEADER_FOKUS-REF_SCHEMAC = WRF_REF_RFS-REF_SCHEMA
WRF_REF_RFS
MANDT [CLNT (3)]
REF_SCHEMA [CHAR (2)]
0..N