SAP ABAP table FCOMS_GROUP_ORDER_ATTR {order attribution in group display}

FCOMS_GROUP_ORDER_ATTR

MANDT	[CLNT (3)]
AUART	[CHAR (4)]
REFNR	[CHAR (12)]
BUKRS	[CHAR (4)]
WERKS	[CHAR (4)]
GSBER	[CHAR (4)]
KOKRS	[CHAR (4)]
KOSTV	[CHAR (10)]
STORT	[CHAR (10)]
SOWRK	[CHAR (4)]
WAERS	[CUKY (5)]
ESTNR	[NUMC (2)]
VOGRP	[CHAR (4)]
KVEWE	[CHAR (1)]
KAPPL	[CHAR (2)]
KALSM	[CHAR (6)]
ABKRS	[NUMC (2)]
KSTAR	[CHAR (10)]
KOSTL	[CHAR (10)]
SAKNR	[CHAR (10)]
CYCLE	[CHAR (10)]
OBJNR	[CHAR (22)]
PRCTR	[CHAR (10)]
PSPEL	[NUMC (8)]
AWSLS	[CHAR (6)]
ABGSL	[CHAR (6)]
TXJCD	[CHAR (15)]
FUNC_AREA	[CHAR (16)]
KDAUF	[CHAR (10)]
IVPRO	[CHAR (6)]
LOGSYSTEM	[CHAR (10)]
ABUKR	[CHAR (4)]
AKSTL	[CHAR (10)]
SIZECL	[CHAR (2)]
IZWEK	[CHAR (2)]
UMWKZ	[CHAR (5)]
ZSCHM	[CHAR (7)]
ANFAUFNR	[CHAR (12)]
BEMOT	[CHAR (2)]
VERAA_USER	[CHAR (12)]
VNAME	[CHAR (6)]
RECID	[CHAR (2)]
ETYPE	[CHAR (3)]
JV_JIBCL	[CHAR (3)]
JV_JIBSA	[CHAR (5)]
FERC_IND	[CHAR (4)]

FCOMS_GROUP_ORDER_ATTR-ANFAUFNR = AUFK-AUFNR (0..N)

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

FCOMS_GROUP_ORDER_ATTR-REFNR = AUFK-AUFNR (0..N)

FCOMS_GROUP_ORDER_ATTR-PRCTR = CEPC-PRCTR (0..N)

CEPC
MANDT [CLNT (3)]
PRCTR [CHAR (10)]
DATBI [DATS (8)]
KOKRS [CHAR (4)]

FCOMS_GROUP_ORDER_ATTR-KSTAR = CSKB-KSTAR (0..N)

CSKB
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KSTAR [CHAR (10)]
DATBI [DATS (8)]

FCOMS_GROUP_ORDER_ATTR-AKSTL = CSKS-KOSTL (0..N)

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

FCOMS_GROUP_ORDER_ATTR-CYCLE = CSKS-KOSTL (0..N)

FCOMS_GROUP_ORDER_ATTR-KOSTL = CSKS-KOSTL (0..N)

FCOMS_GROUP_ORDER_ATTR-KOSTV = CSKS-KOSTL (0..N)

FCOMS_GROUP_ORDER_ATTR-FERC_IND = FERC_C7-IND (0..N)

FERC_C7
MANDT [CLNT (3)]
IND [CHAR (4)]

FCOMS_GROUP_ORDER_ATTR-OBJNR = ONR00-OBJNR (1)

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

FCOMS_GROUP_ORDER_ATTR-PSPEL = PRPS-PSPNR (0..N)

PRPS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]

FCOMS_GROUP_ORDER_ATTR-SAKNR = SKB1-SAKNR (0..N)

SKB1
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
SAKNR [CHAR (10)]

FCOMS_GROUP_ORDER_ATTR-MANDT = T000-MANDT (0..N)

T000
MANDT [CLNT (3)]

FCOMS_GROUP_ORDER_ATTR-ABUKR = T001-BUKRS (0..N)

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

FCOMS_GROUP_ORDER_ATTR-BUKRS = T001-BUKRS (0..N)

FCOMS_GROUP_ORDER_ATTR-SOWRK = T001W-WERKS (0..N)

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

FCOMS_GROUP_ORDER_ATTR-WERKS = T001W-WERKS (0..N)

FCOMS_GROUP_ORDER_ATTR-AUART = T003O-AUART (0..N)

T003O
CLIENT [CLNT (3)]
AUART [CHAR (4)]

FCOMS_GROUP_ORDER_ATTR-IZWEK = T087I-IZWEK (0..N)

T087I
MANDT [CLNT (3)]
IZWEK [CHAR (2)]

FCOMS_GROUP_ORDER_ATTR-UMWKZ = T087K-UMWKZ (0..N)

T087K
MANDT [CLNT (3)]
UMWKZ [CHAR (5)]

FCOMS_GROUP_ORDER_ATTR-STORT = T499S-STAND (0..N)

T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

FCOMS_GROUP_ORDER_ATTR-KAPPL = T681A-KAPPL (0..N)

T681A
KAPPL [CHAR (2)]

FCOMS_GROUP_ORDER_ATTR-KVEWE = T681V-KVEWE (0..N)

T681V
KVEWE [CHAR (1)]

FCOMS_GROUP_ORDER_ATTR-KALSM = T683-KALSM (0..N)

T683
MANDT [CLNT (3)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KALSM [CHAR (6)]

FCOMS_GROUP_ORDER_ATTR-JV_JIBCL = T8J6A-CLASS (0..N)

T8J6A
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
CLASS [CHAR (3)]

FCOMS_GROUP_ORDER_ATTR-JV_JIBSA = T8J6C-SUBCLASS (0..N)

T8J6C
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
CLASS [CHAR (3)]
SUBCLASS [CHAR (5)]

FCOMS_GROUP_ORDER_ATTR-ETYPE = T8JG-ETYPE (0..N)

T8JG
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VNAME [CHAR (6)]
ETYPE [CHAR (3)]
FDATE [NUMC (8)]

FCOMS_GROUP_ORDER_ATTR-RECID = T8JI-RECID (0..N)

T8JI
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
RECID [CHAR (2)]

FCOMS_GROUP_ORDER_ATTR-VNAME = T8JV-VNAME (0..N)

T8JV
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VNAME [CHAR (6)]

FCOMS_GROUP_ORDER_ATTR-SIZECL = TAIF5-SIZECL (0..N)

TAIF5
MANDT [CLNT (3)]
SIZECL [CHAR (2)]

FCOMS_GROUP_ORDER_ATTR-IVPRO = TAPRF-IVPRO (0..N)

TAPRF
MANDT [CLNT (3)]
IVPRO [CHAR (6)]

FCOMS_GROUP_ORDER_ATTR-LOGSYSTEM = TBDLS-LOGSYS (0..N)

TBDLS
LOGSYS [CHAR (10)]

FCOMS_GROUP_ORDER_ATTR-BEMOT = TBMOT-BEMOT (0..N)

TBMOT
MANDT [CLNT (3)]
BEMOT [CHAR (2)]

FCOMS_GROUP_ORDER_ATTR-WAERS = TCURC-WAERS (0..N)

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

FCOMS_GROUP_ORDER_ATTR-FUNC_AREA = TFKB-FKBER (0..N)

TFKB
MANDT [CLNT (3)]
FKBER [CHAR (16)]

FCOMS_GROUP_ORDER_ATTR-GSBER = TGSB-GSBER (0..N)

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

FCOMS_GROUP_ORDER_ATTR-KOKRS = TKA01-KOKRS (0..N)

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

FCOMS_GROUP_ORDER_ATTR-VOGRP = TKAVG-GRUPPE (0..N)

TKAVG
MANDT [CLNT (3)]
OBJID [CHAR (1)]
GRUPPE [CHAR (4)]
ACTIVITY [CHAR (4)]

FCOMS_GROUP_ORDER_ATTR-ABGSL = TKKAA-ABGSL (0..N)

TKKAA
MANDT [CLNT (3)]
ABGSL [CHAR (6)]

FCOMS_GROUP_ORDER_ATTR-ESTNR = TKO03-ASTNR (0..N)

TKO03
CLIENT [CLNT (3)]
ART [CHAR (4)]
ASTNR [NUMC (2)]

FCOMS_GROUP_ORDER_ATTR-ABKRS = TKO08-ABKRS (0..N)

TKO08
CLIENT [CLNT (3)]
KOKRS [CHAR (4)]
ABKRS [NUMC (2)]

FCOMS_GROUP_ORDER_ATTR-AWSLS = TKV01-AWSLS (0..N)

TKV01
MANDT [CLNT (3)]
AWOBA [CHAR (2)]
AWSLS [CHAR (6)]

FCOMS_GROUP_ORDER_ATTR-ZSCHM = TPI01-ZSCHM (0..N)

TPI01
MANDT [CLNT (3)]
ZSCHM [CHAR (7)]

FCOMS_GROUP_ORDER_ATTR-TXJCD = TTXJ-TXJCD (0..N)

TTXJ
MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (15)]

FCOMS_GROUP_ORDER_ATTR-VERAA_USER = USR02-BNAME (0..N)

USR02
MANDT [CLNT (3)]
BNAME [CHAR (12)]

FCOMS_GROUP_ORDER_ATTR-KDAUF = VBUK-VBELN (0..N)

VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]