SAP ABAP table FKKORDERALVPOS {Requests: Structure for ALV Grid with Version}

FKKORDERALVPOS
- *BUKRS_BP* [CHAR (4)]
- *GPART* [CHAR (10)]
- *VKONT* [CHAR (12)]
- *HVORG* [CHAR (4)]
- *TVORG* [CHAR (4)]
- *HKONT_BP* [CHAR (10)]
- *GSBER* [CHAR (4)]
- *SEGMENT* [CHAR (10)]
- *SPART* [CHAR (2)]
- *MWSKZ* [CHAR (2)]
- *SPZAH* [CHAR (1)]
- *MAHNV* [CHAR (2)]
- *IKEY* [CHAR (2)]
- *MANSP* [CHAR (1)]
- *SPERZ* [CHAR (1)]
- *CLRLO* [CHAR (1)]
- *EMGPA* [CHAR (10)]
- *PERSL* [CHAR (4)]
- *BUKRS* [CHAR (4)]
- *HKONT* [CHAR (10)]
- *PRCTR* [CHAR (10)]
- *KOSTL* [CHAR (10)]
- *AUFNR* [CHAR (12)]
- *KDAUF* [CHAR (10)]
- *PS_PSP_PNR* [NUMC (8)]
- *TXJCD* [CHAR (15)]
- *FDGRP* [CHAR (10)]
- *FDLEV* [CHAR (2)]
- *ANLN1* [CHAR (12)]
- *ANLN2* [CHAR (4)]
- *ANBWA* [CHAR (3)]

FKKORDERALVPOS-ANLN2 = ANLA-ANLN2 (0..N)

ANLA
- MANDT [CLNT (3)]
- *BUKRS* [CHAR (4)]
- *ANLN1* [CHAR (12)]
- ANLN2 [CHAR (4)]

FKKORDERALVPOS-ANLN1 = ANLH-ANLN1 (0..N)

ANLH
- MANDT [CLNT (3)]
- *BUKRS* [CHAR (4)]
- ANLN1 [CHAR (12)]

FKKORDERALVPOS-AUFNR = AUFK-AUFNR (0..N)

AUFK
- *MANDT* [CLNT (3)]
- AUFNR [CHAR (12)]

FKKORDERALVPOS-EMGPA = BUT000-PARTNER (0..N)

BUT000
- *CLIENT* [CLNT (3)]
- PARTNER [CHAR (10)]

FKKORDERALVPOS-GPART = BUT000-PARTNER (0..N)

CEPC
- *MANDT* [CLNT (3)]
- PRCTR [CHAR (10)]
- DATBI [DATS (8)]
- *KOKRS* [CHAR (4)]

FKKORDERALVPOS-PRCTR = CEPC-PRCTR (0..N)

CSKS
- MANDT [CLNT (3)]
- *KOKRS* [CHAR (4)]
- KOSTL [CHAR (10)]
- DATBI [DATS (8)]

FKKORDERALVPOS-KOSTL = CSKS-KOSTL (0..N)

FAGL_SEGM
- MANDT [CLNT (3)]
- SEGMENT [CHAR (10)]

FKKORDERALVPOS-SEGMENT = FAGL_SEGM-SEGMENT (0..N)

FKKVK
- *MANDT* [CLNT (3)]
- VKONT [CHAR (12)]

FKKORDERALVPOS-VKONT = FKKVK-VKONT (0..N)

PRPS
- *MANDT* [CLNT (3)]
- PSPNR [NUMC (8)]

FKKORDERALVPOS-PS_PSP_PNR = PRPS-PSPNR (0..N)

SKA1
- *MANDT* [CLNT (3)]
- *KTOPL* [CHAR (4)]
- SAKNR [CHAR (10)]

FKKORDERALVPOS-HKONT = SKA1-SAKNR (0..N)

FKKORDERALVPOS-HKONT_BP = SKA1-SAKNR (0..N)

T001
- *MANDT* [CLNT (3)]
- BUKRS [CHAR (4)]

FKKORDERALVPOS-BUKRS = T001-BUKRS (0..N)

FKKORDERALVPOS-BUKRS_BP = T001-BUKRS (0..N)

T007A
- *MANDT* [CLNT (3)]
- *KALSM* [CHAR (6)]
- MWSKZ [CHAR (2)]

FKKORDERALVPOS-MWSKZ = T007A-MWSKZ (0..N)

T035
- *MANDT* [CLNT (3)]
- GRUPP [CHAR (10)]

FKKORDERALVPOS-FDGRP = T035-GRUPP (0..N)

FKKORDERALVPOS-FDLEV = T036-EBENE (0..N)

T036
- *MANDT* [CLNT (3)]
- EBENE [CHAR (2)]

FKKORDERALVPOS-ANBWA = TABW-BWASL (0..N)

TABW
- *MANDT* [CLNT (3)]
- BWASL [CHAR (3)]

FKKORDERALVPOS-CLRLO = TFK000S-SPPOS (0..N)

TFK000S
- *MANDT* [CLNT (3)]
- SPPOS [CHAR (1)]

FKKORDERALVPOS-PERSL = TFK001P-PERSL (0..N)

TFK001P
- MANDT [CLNT (3)]
- PERSL [CHAR (4)]

FKKORDERALVPOS-SPZAH = TFK008-ZAHLS (0..N)

TFK008
- *MANDT* [CLNT (3)]
- ZAHLS [CHAR (1)]

FKKORDERALVPOS-MAHNV = TFK047A-MAHNV (0..N)

TFK047A
- *MANDT* [CLNT (3)]
- MAHNV [CHAR (2)]

FKKORDERALVPOS-MANSP = TFK047S-MANSP (0..N)

TFK047S
- *MANDT* [CLNT (3)]
- MANSP [CHAR (1)]

FKKORDERALVPOS-IKEY = TFK056A-IKEY (0..N)

TFK056A
- *MANDT* [CLNT (3)]
- IKEY [CHAR (2)]

FKKORDERALVPOS-SPERZ = TFK056S-SPERZ (0..N)

TFK056S
- *MANDT* [CLNT (3)]
- SPERZ [CHAR (1)]

FKKORDERALVPOS-HVORG = TFKHVO-HVORG (0..N)

TFKHVO
- MANDT [CLNT (3)]
- APPLK [CHAR (1)]
- HVORG [CHAR (4)]

FKKORDERALVPOS-TVORG = TFKTVO-TVORG (0..N)

TFKTVO
- MANDT [CLNT (3)]
- APPLK [CHAR (1)]
- *HVORG* [CHAR (4)]
- TVORG [CHAR (4)]

FKKORDERALVPOS-GSBER = TGSB-GSBER (0..N)

TGSB
- MANDT [CLNT (3)]
- GSBER [CHAR (4)]

FKKORDERALVPOS-SPART = TSPA-SPART (0..N)

TSPA
- MANDT [CLNT (3)]
- SPART [CHAR (2)]

FKKORDERALVPOS-TXJCD = TTXJ-TXJCD (0..N)

TTXJ
- *MANDT* [CLNT (3)]
- *KALSM* [CHAR (6)]
- TXJCD [CHAR (15)]

FKKORDERALVPOS-KDAUF = VBUK-VBELN (0..N)

VBUK
- *MANDT* [CLNT (3)]
- VBELN [CHAR (10)]