SAP ABAP table ISMAM_TXW_JGTGPNR {DART IS-M: Central Business Partner Table}

ISMAM_TXW_JGTGPNR

MANDT [CLNT (3)]
JKTOKD [CHAR (4)]
BEGRU [CHAR (4)]
BERUFSL [CHAR (8)]
GFORM [CHAR (2)]
BRSCH [CHAR (4)]
BRAN1 [CHAR (10)]
BRAN2 [CHAR (10)]
BRAN3 [CHAR (10)]
BRAN4 [CHAR (10)]
BRAN5 [CHAR (10)]
JFAMST [CHAR (1)]
GPHERK [CHAR (2)]
KUNNR [CHAR (10)]
LIFNR [CHAR (10)]
GPKLA1 [CHAR (4)]
GPKLA2 [CHAR (4)]
GPKLA3 [CHAR (4)]
GPKLA4 [CHAR (4)]
GPKLA5 [CHAR (4)]
KATR1 [CHAR (2)]
KATR2 [CHAR (2)]
KATR3 [CHAR (2)]
KATR4 [CHAR (2)]
KATR5 [CHAR (2)]
KATR6 [CHAR (3)]
KATR7 [CHAR (3)]
KATR8 [CHAR (3)]
KATR9 [CHAR (3)]
KATR10 [CHAR (3)]
AUFORG [CHAR (4)]
VERLVKORG [CHAR (4)]
AGEN_GRU [CHAR (1)]
GP_DUB [CHAR (1)]
BON [CHAR (2)]
RECHZENTNR [CHAR (2)]
WBZZLSCH [CHAR (1)]
ADRNR [CHAR (10)]
ISPCART [NUMC (1)]

ISMAM_TXW_JGTGPNR-ADRNR = JGTSADR-ADRNR (1..N)

JGTSADR
MANDT [CLNT (3)]
ADRNR [CHAR (10)]

ISMAM_TXW_JGTGPNR-KUNNR = KNA1-KUNNR (1)

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

ISMAM_TXW_JGTGPNR-LIFNR = LFA1-LIFNR (1)

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

ISMAM_TXW_JGTGPNR-MANDT = T000-MANDT (0..N)

T000
MANDT [CLNT (3)]

ISMAM_TXW_JGTGPNR-BRSCH = T016-BRSCH (0..N)

T016
MANDT [CLNT (3)]
BRSCH [CHAR (4)]

ISMAM_TXW_JGTGPNR-BRAN1 = TBRC-BRACO (0..N)
ISMAM_TXW_JGTGPNR-BRAN2 = TBRC-BRACO (0..N)
ISMAM_TXW_JGTGPNR-BRAN3 = TBRC-BRACO (0..N)
ISMAM_TXW_JGTGPNR-BRAN4 = TBRC-BRACO (0..N)
ISMAM_TXW_JGTGPNR-BRAN5 = TBRC-BRACO (0..N)

TBRC
MANDT [CLNT (3)]
BRACO [CHAR (10)]

ISMAM_TXW_JGTGPNR-BEGRU = TBRG-BRGRU (0..N)

TBRG
MANDT [CLNT (3)]
BROBJ [CHAR (10)]
BRGRU [CHAR (4)]

ISMAM_TXW_JGTGPNR-BERUFSL = TJG05-BERUFSL (0..N)

TJG05
MANDT [CLNT (3)]
BERUFSL [CHAR (8)]

ISMAM_TXW_JGTGPNR-JKTOKD = TJG37-JKTOKD (0..N)

TJG37
MANDT [CLNT (3)]
JKTOKD [CHAR (4)]

ISMAM_TXW_JGTGPNR-GPHERK = TJG41-GPHERK (0..N)

TJG41
MANDT [CLNT (3)]
GPHERK [CHAR (2)]

ISMAM_TXW_JGTGPNR-JFAMST = TJG45-JFAMST (0..N)

TJG45
MANDT [CLNT (3)]
JFAMST [CHAR (1)]

ISMAM_TXW_JGTGPNR-GPKLA1 = TJG51-GPKLA (0..N)

TJG51
MANDT [CLNT (3)]
GPKLA [CHAR (4)]

ISMAM_TXW_JGTGPNR-GPKLA2 = TJG53-GPKLA2 (0..N)

TJG53
MANDT [CLNT (3)]
GPKLA2 [CHAR (4)]

ISMAM_TXW_JGTGPNR-GPKLA3 = TJG55-GPKLA3 (0..N)

TJG55
MANDT [CLNT (3)]
GPKLA3 [CHAR (4)]

ISMAM_TXW_JGTGPNR-GPKLA4 = TJG57-GPKLA4 (0..N)

TJG57
MANDT [CLNT (3)]
GPKLA4 [CHAR (4)]

ISMAM_TXW_JGTGPNR-GPKLA5 = TJG59-GPKLA5 (0..N)

TJG59
MANDT [CLNT (3)]
GPKLA5 [CHAR (4)]

ISMAM_TXW_JGTGPNR-GP_DUB = TJGJ0-DUBIOS (1)

TJGJ0
MANDT [CLNT (3)]
DUBIOS [CHAR (1)]

ISMAM_TXW_JGTGPNR-BON = TJGJ2-BONITAET (1)

TJGJ2
MANDT [CLNT (3)]
BONITAET [CHAR (2)]

ISMAM_TXW_JGTGPNR-AGEN_GRU = TJGJ4-AGEN_GRU (1)

TJGJ4
MANDT [CLNT (3)]
AGEN_GRU [CHAR (1)]

ISMAM_TXW_JGTGPNR-ISPCART = TJGR1-ISPCART (1)

TJGR1
MANDT [CLNT (3)]
ISPCART [NUMC (1)]

ISMAM_TXW_JGTGPNR-WBZZLSCH = TJK42-ZLSCH (1)

TJK42
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
ZLSCH [CHAR (1)]

ISMAM_TXW_JGTGPNR-RECHZENTNR = TJKW0-RECHZENTNR (1)

TJKW0
MANDT [CLNT (3)]
RECHZENTNR [CHAR (2)]

ISMAM_TXW_JGTGPNR-AUFORG = TVBUR-VKBUR (1)

TVBUR
MANDT [CLNT (3)]
VKBUR [CHAR (4)]

ISMAM_TXW_JGTGPNR-GFORM = TVGF-GFORM (1)

TVGF
MANDT [CLNT (3)]
GFORM [CHAR (2)]

ISMAM_TXW_JGTGPNR-KATR10 = TVK0-KATR10 (1)

TVK0
MANDT [CLNT (3)]
KATR10 [CHAR (3)]

ISMAM_TXW_JGTGPNR-KATR1 = TVK1-KATR1 (1)

TVK1
MANDT [CLNT (3)]
KATR1 [CHAR (2)]

ISMAM_TXW_JGTGPNR-KATR2 = TVK2-KATR2 (1)

TVK2
MANDT [CLNT (3)]
KATR2 [CHAR (2)]

ISMAM_TXW_JGTGPNR-KATR3 = TVK3-KATR3 (1)

TVK3
MANDT [CLNT (3)]
KATR3 [CHAR (2)]

ISMAM_TXW_JGTGPNR-KATR4 = TVK4-KATR4 (1)

TVK4
MANDT [CLNT (3)]
KATR4 [CHAR (2)]

ISMAM_TXW_JGTGPNR-KATR5 = TVK5-KATR5 (1)

TVK5
MANDT [CLNT (3)]
KATR5 [CHAR (2)]

ISMAM_TXW_JGTGPNR-KATR6 = TVK6-KATR6 (1)

TVK6
MANDT [CLNT (3)]
KATR6 [CHAR (3)]

ISMAM_TXW_JGTGPNR-KATR7 = TVK7-KATR7 (1)

TVK7
MANDT [CLNT (3)]
KATR7 [CHAR (3)]

ISMAM_TXW_JGTGPNR-KATR8 = TVK8-KATR8 (1)

TVK8
MANDT [CLNT (3)]
KATR8 [CHAR (3)]

ISMAM_TXW_JGTGPNR-KATR9 = TVK9-KATR9 (1)

TVK9
MANDT [CLNT (3)]
KATR9 [CHAR (3)]

ISMAM_TXW_JGTGPNR-VERLVKORG = TVKO-VKORG (1)

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]