SAP ABAP table KOMGFNEW {Condition Index: New Entries in Index}




KOMGFNEW-J_1ATXREL = J_1ATXREL-J_1ATXREL
0..N
J_1ATXREL
MANDT [CLNT (3)]
J_1ATXREL [CHAR (10)]
KOMGFNEW-CNAE = J_1BTCNAE-J_1BCNAE
0..N
J_1BTCNAE
MANDT [CLNT (3)]
J_1BCNAE [CHAR (7)]
KOMGFNEW-COMSIZE = J_1BTCOMSIZE-J_1BCOMSIZE
0..N
J_1BTCOMSIZE
MANDT [CLNT (3)]
J_1BCOMSIZE [CHAR (2)]
KOMGFNEW-DECREGPC = J_1BTDECREGPC-J_1BDECREGPC
0..N
J_1BTDECREGPC
MANDT [CLNT (3)]
J_1BDECREGPC [CHAR (2)]
KOMGFNEW-ICMSTAXPAY = J_1BTICMSTAXPAY-J_1BICMSTAXPAY
0..N
J_1BTICMSTAXPAY
MANDT [CLNT (3)]
J_1BICMSTAXPAY [CHAR (2)]
KOMGFNEW-INDTYP = J_1BTINDTYP-J_1BINDTYP
0..N
J_1BTINDTYP
MANDT [CLNT (3)]
J_1BINDTYP [CHAR (2)]
KOMGFNEW-LEGALNAT = J_1BTLEGALNAT-J_1BLEGALNAT
0..N
J_1BTLEGALNAT
MANDT [CLNT (3)]
J_1BLEGALNAT [NUMC (4)]
KOMGFNEW-TDT = J_1BTTDT-J_1BTDT
0..N
J_1BTTDT
MANDT [CLNT (3)]
J_1BTDT [CHAR (2)]
KOMGFNEW-HIENR = KNA1-KUNNR
KOMGFNEW-KUNAG = KNA1-KUNNR
KOMGFNEW-KUNNR = KNA1-KUNNR
KOMGFNEW-KUNRE = KNA1-KUNNR
KOMGFNEW-KUNRG = KNA1-KUNNR
KOMGFNEW-KUNWE = KNA1-KUNNR
0..N
KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]
KOMGFNEW-KNUMA_AG = KONA-KNUMA
KOMGFNEW-KNUMA_PI = KONA-KNUMA
KOMGFNEW-KNUMA_SD = KONA-KNUMA
KOMGFNEW-KNUMA_SQ = KONA-KNUMA
0..N
KONA
MANDT [CLNT (3)]
KNUMA [CHAR (10)]
KOMGFNEW-BBYNR = KONBBYH-BBYNR
0..N
KONBBYH
MANDT [CLNT (3)]
BBYNR [CHAR (12)]
KOMGFNEW-AUSFU = LFA1-LIFNR
KOMGFNEW-HERSE = LFA1-LIFNR
KOMGFNEW-KOLIF = LFA1-LIFNR
KOMGFNEW-LHIENR = LFA1-LIFNR
KOMGFNEW-LIFNR = LFA1-LIFNR
KOMGFNEW-LIFRE = LFA1-LIFNR
KOMGFNEW-LLIEF = LFA1-LIFNR
KOMGFNEW-TDLNR = LFA1-LIFNR
KOMGFNEW-TDLNR_FA = LFA1-LIFNR
0..N
LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
KOMGFNEW-MATNR = MARA-MATNR
0..N
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
0..N
MCHA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
CHARG [CHAR (10)]
0..N
MSR_C_RET_REASON
MANDT [CLNT (3)]
RET_REASON [CHAR (3)]
0..N
MSR_C_RET_REFUND
MANDT [CLNT (3)]
RETURNS_REFUND [CHAR (3)]


KOMGFNEW
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
KUNNR [CHAR (10)]
KDGRP [CHAR (2)]
PLTYP [CHAR (2)]
KONDA [CHAR (2)]
KONDM [CHAR (2)]
WAERK [CUKY (5)]
MATNR [CHAR (18)]
BWTAR [CHAR (10)]
CHARG [CHAR (10)]
PRODH [CHAR (18)]
MEINS [UNIT (3)]
BONUS [CHAR (2)]
PROVG [CHAR (2)]
ALAND [CHAR (3)]
WKREG [CHAR (3)]
LLAND [CHAR (3)]
REGIO [CHAR (3)]
COUNC [CHAR (3)]
CITYC [CHAR (4)]
TAXM1 [CHAR (1)]
TAXM2 [CHAR (1)]
TAXM3 [CHAR (1)]
TAXM4 [CHAR (1)]
TAXM5 [CHAR (1)]
TAXM6 [CHAR (1)]
TAXM7 [CHAR (1)]
KOMGFNEW-UPMAT = MARA-MATNR
KOMGFNEW-VHILM = MARA-MATNR
KOMGFNEW-CHARG = MCHA-CHARG
KOMGFNEW-MSR_RET_REASON = MSR_C_RET_REASON-RET_REASON
KOMGFNEW-MSR_REFUND_CODE = MSR_C_RET_REFUND-RETURNS_REFUND
KOMGFNEW-MANDT = T000-MANDT
KOMGFNEW-BUKRS = T001-BUKRS
KOMGFNEW-RESWK = T001W-WERKS
KOMGFNEW-WERKS = T001W-WERKS
KOMGFNEW-WERKV = T001W-WERKS
KOMGFNEW-AUART = T003O-AUART
KOMGFNEW-ALAND = T005-LAND1
KOMGFNEW-HERKL = T005-LAND1
KOMGFNEW-HLAND = T005-LAND1
KOMGFNEW-LAND1 = T005-LAND1
KOMGFNEW-LAND1A = T005-LAND1
KOMGFNEW-LAND1Z = T005-LAND1
KOMGFNEW-LANDT = T005-LAND1
KOMGFNEW-LLAND = T005-LAND1
KOMGFNEW-SLAND1_A = T005-LAND1
KOMGFNEW-SLAND1_Z = T005-LAND1
KOMGFNEW-TDLNR_LND = T005-LAND1
KOMGFNEW-VERLD = T005-LAND1
KOMGFNEW-COUNC = T005E-COUNC
KOMGFNEW-CITYC = T005G-CITYC
KOMGFNEW-J_1AREGIO = T005S-BLAND
KOMGFNEW-REGIO = T005S-BLAND
KOMGFNEW-REGIOA = T005S-BLAND
KOMGFNEW-REGIOZ = T005S-BLAND
T000
MANDT [CLNT (3)]
T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
T003O
CLIENT [CLNT (3)]
AUART [CHAR (4)]
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
T005E
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
COUNC [CHAR (3)]
T005G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
CITYC [CHAR (4)]
T005S
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
T016
MANDT [CLNT (3)]
BRSCH [CHAR (4)]
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]
T134
MANDT [CLNT (3)]
MTART [CHAR (4)]
0..N
{0,1}
1

TAXM8 [CHAR (1)]
TAXM9 [CHAR (1)]
TAXK1 [CHAR (1)]
TAXK2 [CHAR (1)]
TAXK3 [CHAR (1)]
TAXK4 [CHAR (1)]
TAXK5 [CHAR (1)]
TAXK6 [CHAR (1)]
TAXK7 [CHAR (1)]
TAXK8 [CHAR (1)]
TAXK9 [CHAR (1)]
LIFNR [CHAR (10)]
MATKL [CHAR (9)]
EKORG [CHAR (4)]
WERKS [CHAR (4)]
RESWK [CHAR (4)]
KOLIF [CHAR (10)]
LTSNR [CHAR (6)]
WERKV [CHAR (4)]
VRKME [UNIT (3)]
GSBER [CHAR (4)]
AUART [CHAR (4)]
ZSCHL [CHAR (6)]
KOSTV [CHAR (10)]
MEEIN [UNIT (3)]
KOKRS [CHAR (4)]
KOSAR [CHAR (1)]
INFNR [CHAR (10)]
EVRTN [CHAR (10)]
EVRTP [NUMC (5)]
INCO1 [CHAR (3)]
BUKRS [CHAR (4)]
MTART [CHAR (4)]
LLIEF [CHAR (10)]
LIFRE [CHAR (10)]
BSTME [UNIT (3)]
TAXIM [CHAR (1)]
TAXIK [CHAR (1)]
TAXIW [CHAR (1)]
TXJCD [CHAR (15)]
ERKRS [CHAR (4)]
VERSI [CHAR (3)]
VERSN [CHAR (3)]
VRGAR [CHAR (1)]
FKART [CHAR (4)]
VKORGAU [CHAR (4)]
HIENR [CHAR (10)]
VARCOND [CHAR (26)]
LAND1 [CHAR (3)]
ZTERM [CHAR (4)]
GZOLX [CHAR (4)]
PWGGR [CHAR (6)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
UPMAT [CHAR (18)]
UKONM [CHAR (2)]
AUART_SD [CHAR (4)]
BUGRP [CHAR (6)]
VSTEL [CHAR (4)]

KOMGFNEW-WKREG = T005S-BLAND
KOMGFNEW-BSTME = T006-MSEHI
KOMGFNEW-MEEIN = T006-MSEHI
KOMGFNEW-MEINS = T006-MSEHI
KOMGFNEW-VRKME = T006-MSEHI
KOMGFNEW-BRSCH = T016-BRSCH
KOMGFNEW-MATKL = T023-MATKL
KOMGFNEW-EKORG = T024E-EKORG
KOMGFNEW-MTART = T134-MTART
KOMGFNEW-BWTAR = T149D-BWTAR
KOMGFNEW-KDGRP = T151-KDGRP
KOMGFNEW-BZIRK = T171-BZIRK
KOMGFNEW-VSART = T173-VSART
KOMGFNEW-KONDM = T178-KONDM
KOMGFNEW-UKONM = T178-KONDM
KOMGFNEW-PRDHA = T179-PRODH
KOMGFNEW-PRODH = T179-PRODH
KOMGFNEW-KONDA = T188-KONDA
KOMGFNEW-PLTYP = T189-PLTYP
KOMGFNEW-COIMP = T604-STAWN
KOMGFNEW-STAWN = T604-STAWN
KOMGFNEW-GZOLX = T604G-GZOLX
KOMGFNEW-PWGGR = T604WG-PWGGR
KOMGFNEW-COADI = T610A-COADI
KOMGFNEW-CASNR = T610C-CASNR

T149D
MANDT [CLNT (3)]
BWTAR [CHAR (10)]

T151
MANDT [CLNT (3)]
KDGRP [CHAR (2)]

T171
MANDT [CLNT (3)]
BZIRK [CHAR (6)]

T173
MANDT [CLNT (3)]
VSART [CHAR (2)]

T178
MANDT [CLNT (3)]
KONDM [CHAR (2)]

T179
MANDT [CLNT (3)]
PRODH [CHAR (18)]

T188
MANDT [CLNT (3)]
KONDA [CHAR (2)]

T189
MANDT [CLNT (3)]
PLTYP [CHAR (2)]

T604
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
STAWN [CHAR (17)]

T604G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
GZOLX [CHAR (4)]

T604WG
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
PWGGR [CHAR (6)]

T610A
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COADI [CHAR (6)]

T610C
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
CASNR [CHAR (15)]

LPRIO [NUMC (2)]
LSTEL [CHAR (2)]
LADGR [CHAR (4)]
TRAGR [CHAR (4)]
MFRGR [CHAR (8)]
GARVZ [CHAR (6)]
GTART [CHAR (12)]
SHTYP [CHAR (4)]
TPLST [CHAR (4)]
VSBED [CHAR (2)]
ROUTE [CHAR (6)]
ADD01 [CHAR (10)]
ADD02 [CHAR (10)]
ADD03 [CHAR (10)]
ADD04 [CHAR (10)]
TDLNR_FA [CHAR (10)]
VHART [CHAR (4)]
VEGR1 [CHAR (5)]
VEGR2 [CHAR (5)]
VEGR3 [CHAR (5)]
VEGR4 [CHAR (5)]
VEGR5 [CHAR (5)]
VHILM [CHAR (18)]
LANDT [CHAR (3)]
VSART [CHAR (2)]
TDLNR [CHAR (10)]
TDLNR_LND [CHAR (3)]
SDABW [CHAR (4)]
SLAND1_A [CHAR (3)]
SLAND1_Z [CHAR (3)]
KNOTA [CHAR (10)]
LAND1A [CHAR (3)]
LZONEA [CHAR (10)]
REGIOA [CHAR (3)]
TRFZNA [CHAR (10)]
KNOTZ [CHAR (10)]
LAND1Z [CHAR (3)]
LZONEZ [CHAR (10)]
REGIOZ [CHAR (3)]
TRFZNZ [CHAR (10)]
SRVPOS [CHAR (18)]
BZIRK [CHAR (6)]
VKGRP [CHAR (3)]
BRSCH [CHAR (4)]
VKBUR [CHAR (4)]
PRCTR [CHAR (10)]
PPRCTR [CHAR (10)]
REP_MATNR [CHAR (18)]
LHIENR [CHAR (10)]
KDKGR [CHAR (2)]
J_1AFITP [CHAR (2)]
J_1ARFZ [CHAR (1)]
J_1AREGIO [CHAR (3)]
J_1AGICD [CHAR (2)]
J_1ADTYP [CHAR (2)]
J_1ATXREL [CHAR (10)]
VKAUS [CHAR (3)]
J_1AINDXP [CHAR (5)]
HLAND [CHAR (3)]
AUSFU [CHAR (10)]
HERKL [CHAR (3)]
VERLD [CHAR (3)]
COIMP [CHAR (17)]
STAWN [CHAR (17)]
CASNR [CHAR (15)]
EXPRF [CHAR (8)]
COKON [CHAR (6)]
COPHA [CHAR (6)]
COADI [CHAR (6)]

KOMGFNEW-COPHA = T610D-COPHA (1 — 0..N)

T610D
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COPHA [CHAR (6)]

KOMGFNEW-COKON = T610K-COKON (0..N — 0..N)
KOMGFNEW-KTNUM = T610KP-KTPLN (1 — 0..N)

T610K
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COKON [CHAR (6)]

KOMGFNEW-PLNUM = T610KP-KTPLN (0..N — 0..N)

T610KP
MANDT [CLNT (3)]
EILAN [CHAR (3)]
KTPLV [CHAR (2)]
KTPLN [CHAR (10)]

KOMGFNEW-EILGR = T610LG-EILGR (0..N — 0..N)

T610LG
MANDT [CLNT (3)]
EILAN [CHAR (3)]
EILGR [CHAR (10)]

KOMGFNEW-PREFA = T610PA-PREFA (0..N — 0..N)

T610PA
MANDT [CLNT (3)]
EILAN [CHAR (3)]
PREFA [CHAR (10)]

KOMGFNEW-EXPRF = T616-EXPRF (1 — 0..N)

T616
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
EXPRF [CHAR (8)]

KOMGFNEW-MOGRU = T618G-MOGRU (0..N — 0..N)

T618G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
MOGRU [CHAR (6)]

KOMGFNEW-KOTABNR = T681-KOTABNR (0..N — 0..N)

T681
KVEWE [CHAR (1)]
KOTABNR [NUMC (3)]

KOMGFNEW-KAPPL = T681A-KAPPL (0..N — 0..N)

T681A
KAPPL [CHAR (2)]

KOMGFNEW-KSCHL = T685-KSCHL (0..N — 0..N)

T685
MANDT [CLNT (3)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KSCHL [CHAR (4)]

KOMGFNEW-KZUST = T686C-KZUST (0..N — 0..N)

T686C
MANDT [CLNT (3)]
KZUST [CHAR (3)]

KOMGFNEW-KBSTAT = T686E-KBSTAT (1 — 0..N)

T686E
MANDT [CLNT (3)]
KBSTAT [CHAR (2)]

KOMGFNEW-REP_MATNR = T8A60-REP_MATNR (0..N — 1)

T8A60
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
REP_MATNR [CHAR (18)]

KOMGFNEW-BEMOT = TBMOT-BEMOT (0..N — 0..N)

TBMOT
MANDT [CLNT (3)]
BEMOT [CHAR (2)]


HERSE [CHAR (10)]
KTNUM [CHAR (10)]
PLNUM [CHAR (10)]
PREFA [CHAR (10)]
EILGR [CHAR (10)]
DELCO [CHAR (3)]
RESRC [CHAR (10)]
BEMOT [CHAR (2)]
KNUMA_AG [CHAR (10)]
KNUMA_PI [CHAR (10)]
KUNAG [CHAR (10)]
KUNWE [CHAR (10)]
KUNRG [CHAR (10)]
KUNRE [CHAR (10)]
MOGRU [CHAR (6)]
KBSTAT [CHAR (2)]
AUGRU [CHAR (3)]
BBYNR [CHAR (12)]
CNAE [CHAR (7)]
ICMSTAXPAY [CHAR (2)]
INDTYP [CHAR (2)]
TDT [CHAR (2)]
COMSIZE [CHAR (2)]
DECREGPC [CHAR (2)]
LEGALNAT [NUMC (4)]
EXTWG [CHAR (18)]
PRDHA [CHAR (18)]
MSR_RET_REASON [CHAR (3)]
MSR_REFUND_CODE [CHAR (3)]
HIER_ID [CHAR (2)]
NODE [CHAR (18)]
KAPPL [CHAR (2)]
KNUMA_SQ [CHAR (10)]
KNUMA_SD [CHAR (10)]
KOTABNR [NUMC (3)]
KSCHL [CHAR (4)]
KZUST [CHAR (3)]
KOMGFNEW-WAERK = TCURC-WAERS
KOMGFNEW-GTART = TGAR-GTART
KOMGFNEW-GARVZ = TGAV-GARVZ
KOMGFNEW-GSBER = TGSB-GSBER
KOMGFNEW-INCO1 = TINC-INCO1
KOMGFNEW-KOKRS = TKA01-KOKRS
KOMGFNEW-KOSAR = TKA05-KOSAR
KOMGFNEW-ERKRS = TKEB-ERKRS
KOMGFNEW-VERSI = TKVS-VERSI
KOMGFNEW-VERSN = TKVS-VERSI
KOMGFNEW-ZSCHL = TKZSL-ZSCHL
KOMGFNEW-LADGR = TLGR-LADGR
KOMGFNEW-MFRGR = TMFG-MFRGR
KOMGFNEW-TAXIK = TMKK1-TAXIK
KOMGFNEW-TAXIM = TMKM1-TAXIM
KOMGFNEW-TAXIW = TMKW1-TAXIW
KOMGFNEW-LPRIO = TPRIO-LPRIO
KOMGFNEW-TAXK1 = TSKD-TAXKD
KOMGFNEW-TAXK2 = TSKD-TAXKD
KOMGFNEW-TAXK3 = TSKD-TAXKD
KOMGFNEW-TAXK4 = TSKD-TAXKD
KOMGFNEW-TAXK5 = TSKD-TAXKD
KOMGFNEW-TAXK6 = TSKD-TAXKD
KOMGFNEW-TAXK7 = TSKD-TAXKD
KOMGFNEW-TAXK8 = TSKD-TAXKD
KOMGFNEW-TAXK9 = TSKD-TAXKD
KOMGFNEW-TAXM1 = TSKM-TAXKM
TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]
TGAR
MANDT [CLNT (3)]
GARVZ [CHAR (6)]
GTART [CHAR (12)]
TGAV
MANDT [CLNT (3)]
GARVZ [CHAR (6)]
TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]
TINC
MANDT [CLNT (3)]
INCO1 [CHAR (3)]
TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
TKA05
MANDT [CLNT (3)]
KOSAR [CHAR (1)]
TKEB
MANDT [CLNT (3)]
ERKRS [CHAR (4)]
TKVS
MANDT [CLNT (3)]
VERSI [CHAR (3)]
TKZSL
MANDT [CLNT (3)]
ZSCHL [CHAR (6)]
TLGR
MANDT [CLNT (3)]
LADGR [CHAR (4)]
TMFG
MANDT [CLNT (3)]
MFRGR [CHAR (8)]
TMKK1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIK [CHAR (1)]
TMKM1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIM [CHAR (1)]
TMKW1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIW [CHAR (1)]
0..N
1


KOMGFNEW-TAXM2 = TSKM-TAXKM
KOMGFNEW-TAXM3 = TSKM-TAXKM
KOMGFNEW-TAXM4 = TSKM-TAXKM
KOMGFNEW-TAXM5 = TSKM-TAXKM
KOMGFNEW-TAXM6 = TSKM-TAXKM
KOMGFNEW-TAXM7 = TSKM-TAXKM
KOMGFNEW-TAXM8 = TSKM-TAXKM
KOMGFNEW-TAXM9 = TSKM-TAXKM
KOMGFNEW-SPART = TSPA-SPART
KOMGFNEW-TPLST = TTDS-TPLST
KOMGFNEW-TRAGR = TTGR-TRAGR
KOMGFNEW-TXJCD = TTXJ-TXJCD
KOMGFNEW-AUART_SD = TVAK-AUART
KOMGFNEW-VARCOND = TVARC-VARCOND
KOMGFNEW-AUGRU = TVAU-AUGRU
KOMGFNEW-BONUS = TVBO-BONUS
KOMGFNEW-VKBUR = TVBUR-VKBUR
KOMGFNEW-DELCO = TVDC-DELCO
0..N
TPRIO
MANDT [CLNT (3)]
LPRIO [NUMC (2)]
TSKD
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKD [CHAR (1)]
TSKM
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKM [CHAR (1)]
TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]
TTDS
MANDT [CLNT (3)]
TPLST [CHAR (4)]
TTGR
MANDT [CLNT (3)]
TRAGR [CHAR (4)]
TTXJ
MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (15)]
TVAK
MANDT [CLNT (3)]
AUART [CHAR (4)]
TVARC
MANDT [CLNT (3)]
VARCOND [CHAR (26)]
TVAU
MANDT [CLNT (3)]
AUGRU [CHAR (3)]
TVBO
MANDT [CLNT (3)]
BONUS [CHAR (2)]
TVBUR
MANDT [CLNT (3)]
VKBUR [CHAR (4)]
TVDC
MANDT [CLNT (3)]
DELCO [CHAR (3)]


KOMGFNEW-VEGR1 = TVE1-VEGR1
TVE1
MANDT [CLNT (3)]
VEGR1 [CHAR (5)]
0..N
KOMGFNEW-VEGR2 = TVE2-VEGR2
TVE2
MANDT [CLNT (3)]
VEGR2 [CHAR (5)]
0..N
KOMGFNEW-VEGR3 = TVE3-VEGR3
TVE3
MANDT [CLNT (3)]
VEGR3 [CHAR (5)]
0..N
KOMGFNEW-VEGR4 = TVE4-VEGR4
TVE4
MANDT [CLNT (3)]
VEGR4 [CHAR (5)]
0..N
KOMGFNEW-VEGR5 = TVE5-VEGR5
TVE5
MANDT [CLNT (3)]
VEGR5 [CHAR (5)]
0..N
KOMGFNEW-BUGRP = TVFBWG-BUGRP
TVFBWG
MANDT [CLNT (3)]
KAPPL [CHAR (2)]
BUGRP [CHAR (6)]
0..N
KOMGFNEW-FKART = TVFK-FKART
TVFK
MANDT [CLNT (3)]
FKART [CHAR (4)]
0..N
KOMGFNEW-TRFZNA = TVFTZ-TRFZN
KOMGFNEW-TRFZNZ = TVFTZ-TRFZN
TVFTZ
MANDT [CLNT (3)]
TRFZN [CHAR (10)]
0..N
0..N
KOMGFNEW-VRGAR = TVGA-VRGAR
TVGA
MANDT [CLNT (3)]
VRGAR [CHAR (1)]
0..N
KOMGFNEW-KDKGR = TVKGG-KDKGR
TVKGG
MANDT [CLNT (3)]
KDKGR [CHAR (2)]
0..N
KOMGFNEW-VKGRP = TVKGR-VKGRP
TVKGR
MANDT [CLNT (3)]
VKGRP [CHAR (3)]
0..N
KOMGFNEW-KNOTA = TVKN-KNOTE
KOMGFNEW-KNOTZ = TVKN-KNOTE
TVKN
MANDT [CLNT (3)]
KNOTE [CHAR (10)]
0..N
0..N
KOMGFNEW-VKORG = TVKO-VKORG
KOMGFNEW-VKORGAU = TVKO-VKORG
TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]
0..N
0..N
KOMGFNEW-LSTEL = TVLA-LSTEL
TVLA
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
LSTEL [CHAR (2)]
0..N
KOMGFNEW-VKAUS = TVLV-ABRVW
TVLV
MANDT [CLNT (3)]
ABRVW [CHAR (3)]
0..N
KOMGFNEW-PROVG = TVPR-PROVG
TVPR
MANDT [CLNT (3)]
PROVG [CHAR (2)]
0..N


KOMGFNEW-ROUTE = TVRO-ROUTE
TVRO
MANDT [CLNT (3)]
ROUTE [CHAR (6)]
0..N
KOMGFNEW-SDABW = TVSAK-SDABW
TVSAK
MANDT [CLNT (3)]
SDABW [CHAR (4)]
0..N
KOMGFNEW-VSBED = TVSB-VSBED
TVSB
MANDT [CLNT (3)]
VSBED [CHAR (2)]
0..N
KOMGFNEW-VSTEL = TVST-VSTEL
TVST
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
0..N
KOMGFNEW-SHTYP = TVTK-SHTYP
TVTK
MANDT [CLNT (3)]
SHTYP [CHAR (4)]
0..N
KOMGFNEW-VTWEG = TVTW-VTWEG
TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]
0..N
KOMGFNEW-VHART = TVTY-TRATY
TVTY
MANDT [CLNT (3)]
TRATY [CHAR (4)]
0..N
KOMGFNEW-ZTERM = TVZB-ZTERM
TVZB
MANDT [CLNT (3)]
ZTERM [CHAR (4)]
0..N
KOMGFNEW-EXTWG = TWEW-EXTWG
TWEW
MANDT [CLNT (3)]
EXTWG [CHAR (18)]
0..N
KOMGFNEW-LZONEA = TZONE-ZONE1
TZONE
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
ZONE1 [CHAR (10)]
0..N
KOMGFNEW-LZONEZ = TZONE-ZONE1
0..N
KOMGFNEW-VBELN = VBUK-VBELN
VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]
0..N
KOMGFNEW-POSNR = VBUP-POSNR
VBUP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
0..N
KOMGFNEW-ADD01 = VTADD01-ADD_INFO
VTADD01
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
KOMGFNEW-ADD02 = VTADD02-ADD_INFO
VTADD02
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
KOMGFNEW-ADD03 = VTADD03-ADD_INFO
VTADD03
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
KOMGFNEW-ADD04 = VTADD04-ADD_INFO
VTADD04
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
KOMGFNEW-HIER_ID = WRF_MATGRP_HIER-HIER_ID
WRF_MATGRP_HIER
MANDT [CLNT (3)]
HIER_ID [CHAR (2)]
0..N
KOMGFNEW-NODE = WRF_MATGRP_STRUC-NODE
WRF_MATGRP_STRUC
MANDT [CLNT (3)]
HIER_ID [CHAR (2)]
NODE [CHAR (18)]
DATE_FROM [DATS (8)]
0..N
KOMGFNEW-LTSNR = WYT1-LTSNR
WYT1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
LTSNR [CHAR (6)]
0..N