SAP ABAP table MARC_UEB {Field TRANC Added to MARC}


MARC_UEB
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
BWTTY [CHAR (1)]
MMSTA [CHAR (2)]
MAABC [CHAR (1)]
EKGRP [CHAR (3)]
AUSME [UNIT (3)]
DISPR [CHAR (4)]
DISMM [CHAR (2)]
DISPO [CHAR (3)]
DINLS [CHAR (2)]
SOBSL [CHAR (2)]
LAGPR [CHAR (1)]
MPRAF [CHAR (1)]
FHORI [CHAR (3)]
FEVOR [CHAR (3)]
ZZFIX [UNIT (3)]
SFCPF [CHAR (4)]
AUFTL [CHAR (1)]
PLNTY [CHAR (1)]
GTPER [CHAR (2)]
MTAFP [CHAR (2)]
PERIV [CHAR (2)]
LDZEIT [CHAR (4)]
BWSCL [CHAR (1)]
STAWN [CHAR (17)]
HERKL [CHAR (3)]
HERKR [CHAR (3)]
EXPME [UNIT (3)]
MTVFP [CHAR (4)]
MRPPP [CHAR (3)]
STLAN [CHAR (1)]
SOBSK [CHAR (2)]
FRTME [UNIT (3)]
LGPRO [CHAR (4)]
DISGR [CHAR (4)]
QSSYS [CHAR (4)]
RWPRO [CHAR (3)]
ABCIN [CHAR (1)]
AWSLS [CHAR (6)]
SERNP [CHAR (4)]
STDPD [CHAR (18)]
SFEPR [CHAR (4)]
QSSYS [CHAR (4)]
LFMAT [CHAR (18)]
RDPRF [CHAR (4)]
VRBMT [CHAR (18)]
VRBWK [CHAR (4)]
SERIV [CHAR (1)]
STRGR [CHAR (2)]
LGFSB [CHAR (4)]
EPRIO [CHAR (4)]
QMATA [CHAR (6)]
PLNTY [CHAR (1)]
UOMGR [CHAR (3)]
UMREZ [CHAR (5)]
SFCPF [CHAR (4)]
MDACH [CHAR (2)]
MEGRU [CHAR (4)]
MFRGR [CHAR (8)]
LOGGR [CHAR (4)]
FPRFM [CHAR (1)]
MOMNR [CHAR (12)]
MOGRU [CHAR (6)]
CASNR [CHAR (15)]
GPNUM [CHAR (8)]
STEUC [CHAR (16)]
VSPVB [CHAR (5)]
COMPL [NUMC (2)]
CONVT [CHAR (1)]
SHPRO [CHAR (3)]
OCMPF [CHAR (4)]
UCMAT [CHAR (18)]
LPSC_R_PRGRP [CHAR (18)]
ASD_TYPE [CHAR (10)]
CONS_PROCG [CHAR (10)]
REF_SCHEMA [CHAR (22)]
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
MDIP
MANDT [CLNT (3)]
DISPR [CHAR (4)]
OI8D1
MANDT [CLNT (3)]
UMRSL [CHAR (4)]
OI8D6
MANDT [CLNT (3)]
UOMGR [CHAR (3)]
PVBE
MANDT [CLNT (3)]
WERKS [CHAR (4)]
PBVBE [CHAR (5)]
RDPR
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RDZAE [NUMC (6)]
T000
MANDT [CLNT (3)]
T001L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
T005S
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
T009
MANDT [CLNT (3)]
PERIV [CHAR (2)]
T024
MANDT [CLNT (3)]
EKGRP [CHAR (3)]
T024D
MANDT [CLNT (3)]
WERKS [CHAR (4)]
DISPO [CHAR (3)]
T024F
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FEVOR [CHAR (3)]
T141
MANDT [CLNT (3)]
MMSTA [CHAR (2)]
T149C
MANDT [CLNT (3)]
BWTTY [CHAR (1)]
T159C
MANDT [CLNT (3)]
WERKS [CHAR (4)]
ABCIN [CHAR (1)]
T377P
MANDT [CLNT (3)]
SERNL [CHAR (4)]
T416
MANDT [CLNT (3)]
STLAN [CHAR (1)]
T434G
MANDT [CLNT (3)]
WERKS [CHAR (4)]
EPRIO [CHAR (4)]
T436A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FHORI [CHAR (3)]
T437S
MANDT [CLNT (3)]
SFEPR [CHAR (4)]
T438A
MANDT [CLNT (3)]
DISMM [CHAR (2)]
T438M
MANDT [CLNT (3)]
WERKS [CHAR (4)]
MTAFT [CHAR (4)]
T438R
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RWPRO [CHAR (3)]
T438V
MANDT [CLNT (3)]
WERKS [CHAR (4)]
SHPRO [CHAR (3)]
T439A
MANDT [CLNT (3)]
DISLS [CHAR (2)]
T439G
MANDT [CLNT (3)]
WERKS [CHAR (4)]
MRPPP [CHAR (3)]
T439L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LAGPR [CHAR (1)]
T439P
MANDT [CLNT (3)]
WERKS [CHAR (4)]
PERAZ [CHAR (1)]
AUFTL [CHAR (1)]
T460A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
SOBSL [CHAR (2)]
T461P
MANDT [CLNT (3)]
STRGR [CHAR (2)]
T464C
MANDT [CLNT (3)]
MDACH [CHAR (2)]
ACZPR [CHAR (4)]
ACCTO [CHAR (4)]
T604
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
STAWN [CHAR (17)]
T604F
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
STEUC [CHAR (16)]
T609G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
GPNUM [CHAR (8)]
T610C
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
CASNR [CHAR (15)]
T618G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
MOGRU [CHAR (6)]
T618M
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
MOMNR [CHAR (12)]
T778O
MANDT [CLNT (3)]
QTYPE [CHAR (2)]
T778P
MANDT [CLNT (3)]
PVKAR [CHAR (2)]
TCA01
MANDT [CLNT (3)]
PLNTY [CHAR (1)]
TCD43
MANDT [CLNT (3)]
WERKS [CHAR (4)]
CO_PRODPRF [CHAR (6)]
TCD48
MANDT [CLNT (3)]
GPROFILE [CHAR (6)]
TCSCP_COMP_LVL
MANDT [CLNT (3)]
COMP_LEVEL [NUMC (2)]
TCSCP_CONV_TYPE
MANDT [CLNT (3)]
CONV_TYPE [CHAR (2)]
THUD_TYPE
HUD_TYPE [CHAR (10)]
TKV01
MANDT [CLNT (3)]
AWGRA [CHAR (2)]
AWGLS [CHAR (6)]
TLGA
MANDT [CLNT (3)]
LADGR [CHAR (4)]
TLOG
MANDT [CLNT (3)]
LOGGR [CHAR (4)]
TMABC
MANDT [CLNT (3)]
MAABC [CHAR (1)]
TMBWS
MANDT [CLNT (3)]
BWSCL [CHAR (1)]
TMFG
MANDT [CLNT (3)]
MFRGR [CHAR (8)]
TMFPF
MANDT [CLNT (3)]
FPRFM [CHAR (1)]
TMQ2
MANDT [CLNT (3)]
USEQU [CHAR (1)]
TMVF
MANDT [CLNT (3)]
MTVFP [CHAR (2)]
TQ01B
MANDT [CLNT (3)]
QMATAUTH [CHAR (6)]
TQ02
MANDT [CLNT (3)]
QSSYS [CHAR (4)]
TQ05
MANDT [CLNT (3)]
ZGTYP [CHAR (4)]
TQ08
MANDT [CLNT (3)]
QM_PUR [CHAR (8)]
TVFM
MANDT [CLNT (3)]
MTVER [CHAR (4)]
TWMEG
MANDT [CLNT (3)]
MEGRU [CHAR (4)]
MEINS [UNIT (3)]
TWSG
MANDT [CLNT (3)]
SERIVG [CHAR (1)]
WRFT_CONS_PROCG
MANDT [CLNT (3)]
WRF_CONS_PROCG [CHAR (10)]
WRF_REF_RFS
MANDT [CLNT (3)]
REF_SCHEMA [CHAR (22)]
MARC_UEB-VSO_PKGP = TVSOM_PKG-PKGRP
MARC_UEB-MATNR = MARA-MATNR
MARC_UEB-NFMAT = MARA-MATNR
MARC_UEB-STDPD = MARA-MATNR
MARC_UEB-UCMAT = MARA-MATNR
MARC_UEB-VRBMT = MARA-MATNR
MARC_UEB-DISPR = MDIP-DISPR
MARC_UEB-UMRSL = OI8D1-UMRSL
MARC_UEB-UOMGR = OI8D6-UOMGR
MARC_UEB-VSPVB = PVBE-PBVBE
MARC_UEB-RDPRF = RDPR-RDPRF
MARC_UEB-MANDT = T000-MANDT
MARC_UEB-LGFSB = T001L-LGORT
MARC_UEB-LGPRO = T001L-LGORT
MARC_UEB-VRBWK = T001W-WERKS
MARC_UEB-WERKS = T001W-WERKS
MARC_UEB-HERKL = T005-LAND1
MARC_UEB-HERKR = T005S-BLAND
MARC_UEB-AUSME = T006-MSEHI
MARC_UEB-EXPME = T006-MSEHI
MARC_UEB-FRTME = T006-MSEHI
MARC_UEB-LZEIT = T006-MSEHI
MARC_UEB-PERIV = T009-PERIV
MARC_UEB-EKGRP = T024-EKGRP
MARC_UEB-DISPO = T024D-DISPO
MARC_UEB-FEVOR = T024F-FEVOR
MARC_UEB-MMSTA = T141-MMSTA
MARC_UEB-BWTTY = T149C-BWTTY
MARC_UEB-ABCIN = T159C-ABCIN
MARC_UEB-SERNP = T377P-SERNL
MARC_UEB-STLAN = T416-STLAN
MARC_UEB-EPRIO = T434G-EPRIO
MARC_UEB-FHORI = T436A-FHORI
MARC_UEB-SFEPR = T437S-SFEPR
MARC_UEB-DISMM = T438A-DISMM
MARC_UEB-DISGR = T438M-MTART
MARC_UEB-RWPRO = T438R-RWPRO
MARC_UEB-SHPRO = T438V-SHPRO
MARC_UEB-DISLS = T439A-DISLS
MARC_UEB-LFRHY = T439G-MRPPP
MARC_UEB-MRPPP = T439G-MRPPP
MARC_UEB-LAGPR = T439L-LAGPR
MARC_UEB-AUFTL = T439P-AUFTL
MARC_UEB-SOBSK = T460A-SOBSL
MARC_UEB-SOBSL = T460A-SOBSL
MARC_UEB-STRGR = T461P-STRGR
MARC_UEB-MDACH = T464C-MDACH
MARC_UEB-STAWN = T604-STAWN
MARC_UEB-STEUC = T604F-STEUC
MARC_UEB-GPNUM = T609G-GPNUM
MARC_UEB-CASNR = T610C-CASNR
MARC_UEB-MOGRU = T618G-MOGRU
MARC_UEB-MOMNR = T618M-MOMNR
MARC_UEB-QTYPE = T778O-QTYPE
MARC_UEB-PVKAR = T778P-PVKAR
MARC_UEB-PLNTY = TCA01-PLNTY
MARC_UEB-SFCPF = TCD43-CO_PRODPRF
MARC_UEB-OCMPF = TCD48-GPROFILE
MARC_UEB-COMPL = TCSCP_COMP_LVL-COMP_LEVEL
MARC_UEB-CONVT = TCSCP_CONV_TYPE-CONV_TYPE
MARC_UEB-IUID_TYPE = THUD_TYPE-IUID_TYPE
MARC_UEB-AWSLS = TKV01-AWSLS
MARC_UEB-LADGR = TLGA-LADGR
MARC_UEB-LOGGR = TLOG-LOGGR
MARC_UEB-MAABC = TMABC-MAABC
MARC_UEB-BWSCL = TMBWS-BWSCL
MARC_UEB-MFRGR = TMFG-MFRGR
MARC_UEB-FPRFM = TMFPF-FPRFM
MARC_UEB-USEQU = TMQ2-USEQU
MARC_UEB-MTVFP = TMVF-MTVFP
MARC_UEB-QMATA = TQ01B-QMATAUTH
MARC_UEB-QSSYS = TQ02-QSSYS
MARC_UEB-QZGTP = TQ05-ZGTYP
MARC_UEB-SSQSS = TQ08-QM_PUR
MARC_UEB-MTVER = TVFM-MTVER
MARC_UEB-MEGRU = TWMEG-MEGRU
MARC_UEB-SERIVG = TWSG-SERIVG
MARC_UEB-CONS_PROCG = WRFT_CONS_PROCG-WRF_CONS_PROCG
MARC_UEB-REF_SCHEMA = WRF_REF_RFS-REF_SCHEMA
0..N
1
{0,1}
0..N,N
0..N,0..N
0..N,0..N
0..N,0..