SAP ABAP table RJPMARA {IS-M: Structure for MARA}


RJPMARA {IS-M: Structure for MARA}
MANDT [CLNT (3)]
MDART [CHAR (3)]
MBRSH [CHAR (1)]
MATKL [CHAR (9)]
NEINH [UNIT (3)]
BSTME [UNIT (3)]
WRKST [CHAR (480)]
LABOR [CHAR (3)]
EKWSL [CHAR (4)]
GEWEI [UNIT (3)]
VOLEH [UNIT (3)]
BEHVO [CHAR (2)]
RAUBE [CHAR (2)]
TEMPB [CHAR (2)]
TRAGR [CHAR (4)]
STOFF [CHAR (18)]
SPART [CHAR (2)]
KUNNR [CHAR (10)]
RWVOR [CHAR (11)]
BWSCL [CHAR (13)]
SAISO [CHAR (4)]
ETIAR [CHAR (2)]
ETIFO [CHAR (2)]
NUMTP [CHAR (2)]
MEABM [UNIT (3)]
PROHA [CHAR (18)]
ERGEI [UNIT (3)]
ERVOE [UNIT (3)]
YHART [CHAR (4)]
MAGRV [CHAR (4)]
PLGTP [CHAR (2)]
EXTWG [CHAR (18)]
SATNR [CHAR (18)]
PMATA [CHAR (18)]
MSTAE [CHAR (2)]
MSTAV [CHAR (2)]
TAKLV [CHAR (1)]
RMATP [CHAR (9)]
INHME [UNIT (3)]
ETIAG [CHAR (18)]
KOSCH [CHAR (18)]
MFRNR [CHAR (10)]
SMATN [CHAR (18)]
MPROF [CHAR (4)]
SAITY [CHAR (2)]
PROFL [CHAR (3)]
COMPL [NUMC (2)]
MTPOS_MARA [CHAR (4)]
GENNR [CHAR (18)]
RMATP [CHAR (18)]
HUTYP_DFLT [CHAR (4)]
WHSTC [CHAR (2)]
WHMATGR [CHAR (4)]
HNDLCODE [CHAR (4)]
HUTYP [CHAR (4)]
MAXDIM_UOM [UNIT (3)]
HERKL [CHAR (3)]
MFRGR [CHAR (8)]
QQTIMEUOM [UNIT (3)]
QGRP [CHAR (4)]
SERIAL [CHAR (4)]
PS_SMARTFORM [CHAR (30)]
LOGUNIT [UNIT (3)]
CWQPROC [CHAR (2)]
CWQTOLGR [CHAR (99)]
ADPROF [CHAR (3)]
NEDIUM [CHAR (4)]
COMMODITY [CHAR (18)]
ANP [NUMC (5)]
_BEV1_LULDEGRP [CHAR (3)]
_DSD_SL_TOLTYP [CHAR (4)]
_DSD_SV_CNT_GRP [CHAR (18)]
_DSD_VC_GROUP [CHAR (6)]
PACKCODE [CHAR (10)]
DG_PACK_STATUS [CHAR (100)]
IBTAT [CHAR (2)]
BRAND_ID [CHAR (4)]
FIBER_CODE1 [CHAR (3)]
FIBER_CODE2 [CHAR (3)]
FIBER_CODE3 [CHAR (3)]
FIBER_CODE4 [CHAR (3)]
FIBER_CODE5 [CHAR (3)]
FASHGRD [CHAR (4)]
RJPMARA-BEV1/LULDEGRP = /BEV1/LULT906/BEV1/LULDEGRP
0..N
_BEV1_LULT906
MANDT [CLNT (3)]
_BEV1_LULDEGRP [CHAR (3)]
RJPMARA-/DSD/SL_TOLTYP = /DSD/SL_TGTYP-TOLTYP_ID
0..N
_DSD_SL_TGTYP
CLIENT [CLNT (3)]
TOLTYP_ID [CHAR (4)]
RJPMARA-/DSD/SV_CNT_GRP = /DSD/SV_CNTGR-COUNT_GROUP
0..N
_DSD_SV_CNTGR
CLIENT [CLNT (3)]
COUNT_GROUP [CHAR (100)]
RJPMARA-/DSD/VC_GROUP = /DSD/VC_GRP-GRP
0..N
_DSD_VC_GRP
MANDT [CLNT (3)]
GRP [CHAR (6)]
RJPMARA-PACKCODE = CCUNC121-PACKCODE
0..N
CCUNC121
MANDT [CLNT (3)]
UNSG [CHAR (123)]
PACKCODE [CHAR (10)]
RJPMARA-ANP = J_1BTANP1_1BANP
0..N
J_1BTANP
MANDT [CLNT (3)]
J_1BANP [NUMC (5)]
RJPMARA-MFRNR = LFA1-LIFNR
0..N
LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
RJPMARA-IMATN = MARA-MATNR
RJPMARA-GENNR = MARA-MATNR
RJPMARA-PMATA = MARA-MATNR
RJPMARA-RMATP = MARA-MATNR
RJPMARA-SATNR = MARA-MATNR
RJPMARA-LOGUNIT = MARM-MEINH
0..N
0..N
0..N
0..N
1..N
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
MARM
MANDT [CLNT (3)]
MATNR [CHAR (18)]
MEINH [UNIT (3)]
RJPMARA-STOFF = MGEF-STOFF
0..N
MGEF
MANDT [CLNT (3)]
STOFF [CHAR (18)]
RCGKZ [CHAR (3)]
RJPMARA-PS_SMARTFORM = STXFADM-FORMNAME
0..N
STXFADM
FORMNAME [CHAR (30)]
RJPMARA-MANDT = T000-MANDT
0..N
T000
MANDT [CLNT (3)]
RJPMARA-HERKL = T005-LAND1
0..N
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
RJPMARA-BSTME = T006-MSEHI
0..N
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
RJPMARA-ERGEI = T006-MSEHI
RJPMARA-ERVOE = T006-MSEHI
RJPMARA-GEWEI = T006-MSEHI
RJPMARA-MAXDIM_UOM = T006-MSEHI
RJPMARA-MEABM = T006-MSEHI
RJPMARA-MEINS = T006-MSEHI
RJPMARA-QQTIMEUOM = T006-MSEHI
RJPMARA-VOLEH = T006-MSEHI
0..N
0..N
0..N
0..N