SAP ABAP table S032 {Statistics: Current Stock and Grouping Terms}


S032
MANDT [CLNT (3)]
SSOUR [CHAR (4)]
VRSIO [CHAR (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]
MATNR [CHAR (18)]
HWAER [CUKY (5)]
DISPO [CHAR (3)]
MTART [CHAR (4)]
MATKL [CHAR (9)]
DISMM [CHAR (2)]
GSBER [CHAR (4)]
SPART [CHAR (2)]
BKLAS [CHAR (4)]
S032-MATNR = MARA-MATNR
{0,1}
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
S032-MANDT = T000-MANDT
0..N
T000
MANDT [CLNT (3)]
S032-LGORT = T001L-LGORT
0..N
T001L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]
S032-WERKS = T001W-WERKS
0..N
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
S032-MATKL = T023-MATKL
0..N
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
S032-DISPO = T024D-DISPO
0..N
T024D
MANDT [CLNT (3)]
WERKS [CHAR (4)]
DISPO [CHAR (3)]
S032-BKLAS = T025-BKLAS
0..N
T025
MANDT [CLNT (3)]
BKLAS [CHAR (4)]
S032-MTART = T134-MTART
0..N
T134
MANDT [CLNT (3)]
MTART [CHAR (4)]
S032-DISMM = T438A-DISMM
0..N
T438A
MANDT [CLNT (3)]
DISMM [CHAR (2)]
S032-HWAER = TCURC-WAERS
0..N
TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]
S032-GSBER = TGSB-GSBER
0..N
TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]
S032-SPART = TSPA-SPART
0..N
TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]
1
1
1