SAP ABAP table S123E {S123 - Structural Information}


S123E
MANDT [CLNT (3)]
SSOUR [CHAR (4)]
EKORG [CHAR (4)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
BZIRK [CHAR (6)]
WERKS [CHAR (4)]
KUNAG [CHAR (10)]
WGRU2 [CHAR (18)]
WGRU1 [CHAR (18)]
MATKL [CHAR (9)]
BASME [UNIT (3)]
HWAER [CUKY (5)]
PERIV [CHAR (2)]
S123E-KUNAG = KNA1-KUNNR
KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]
S123E-MANDT = T000-MANDT
T000
MANDT [CLNT (3)]
S123E-WERKS = T001W-WERKS
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
S123E-BASME = T006-MSEHI
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
S123E-PERIV = T009-PERIV
T009
MANDT [CLNT (3)]
PERIV [CHAR (2)]
S123E-MATKL = T023-MATKL
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
S123E-EKORG = T024E-EKORG
T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]
S123E-BZIRK = T171-BZIRK
T171
MANDT [CLNT (3)]
BZIRK [CHAR (6)]
S123E-HWAER = TCURC-WAERS
TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]
S123E-VKORG = TVKO-VKORG
TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]
S123E-VTWEG = TVTW-VTWEG
TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]
0..N
1
0..N
0..N
1
0..N
0..N
0..N