SAP ABAP table STR_KOMG {Structure: Fields Permitted for Condition Structures}




STR_KOMG-J_1ATXREL = J_1ATXREL-J_1ATXREL
0..N
J_1ATXREL
MANDT [CLNT (3)]
J_1ATXREL [CHAR (10)]
STR_KOMG-CNAE = J_1BTCNAE-J_1BCNAE
0..N
J_1BTCNAE
MANDT [CLNT (3)]
J_1BCNAE [CHAR (7)]
STR_KOMG-COMSIZE = J_1BTCOMSIZE-J_1BCOMSIZE
0..N
J_1BTCOMSIZE
MANDT [CLNT (3)]
J_1BCOMSIZE [CHAR (2)]
STR_KOMG-DECREGPC = J_1BTDECREGPC-J_1BDECREGPC
0..N
J_1BTDECREGPC
MANDT [CLNT (3)]
J_1BDECREGPC [CHAR (2)]
STR_KOMG-ICMSTAXPAY = J_1BTICMSTAXPAY-J_1BICMSTAXPAY
0..N
J_1BTICMSTAXPAY
MANDT [CLNT (3)]
J_1BICMSTAXPAY [CHAR (2)]
STR_KOMG-INDTYP = J_1BTINDTYP-J_1BINDTYP
0..N
J_1BTINDTYP
MANDT [CLNT (3)]
J_1BINDTYP [CHAR (2)]
STR_KOMG-LEGALNAT = J_1BTLEGALNAT-J_1BLEGALNAT
0..N
J_1BTLEGALNAT
MANDT [CLNT (3)]
J_1BLEGALNAT [NUMC (4)]
STR_KOMG-TDT = J_1BTTDT-J_1BTDT
0..N
J_1BTTDT
MANDT [CLNT (3)]
J_1BTDT [CHAR (2)]
STR_KOMG-HIENR = KNA1-KUNNR
STR_KOMG-KUNAG = KNA1-KUNNR
STR_KOMG-KUNNR = KNA1-KUNNR
STR_KOMG-KUNRE = KNA1-KUNNR
STR_KOMG-KUNRG = KNA1-KUNNR
STR_KOMG-KUNWE = KNA1-KUNNR
0..N
KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]
STR_KOMG-KNUMA_AG = KONA-KNUMA
STR_KOMG-KNUMA_PI = KONA-KNUMA
0..N
KONA
MANDT [CLNT (3)]
KNUMA [CHAR (10)]
STR_KOMG-BBYNR = KONBBYH-BBYNR
0..N
KONBBYH
MANDT [CLNT (3)]
BBYNR [CHAR (12)]
STR_KOMG-AUSFU = LFA1-LIFNR
STR_KOMG-HERSE = LFA1-LIFNR
STR_KOMG-KOLIF = LFA1-LIFNR
STR_KOMG-LHIENR = LFA1-LIFNR
STR_KOMG-LIFNR = LFA1-LIFNR
STR_KOMG-LIFRE = LFA1-LIFNR
STR_KOMG-LLIEF = LFA1-LIFNR
STR_KOMG-TDLNR = LFA1-LIFNR
STR_KOMG-TDLNR_FA = LFA1-LIFNR
0..N
LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
STR_KOMG-MATNR = MARA-MATNR
0..N
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
0..N
MCHA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
CHARG [CHAR (10)]
0..N
MSR_C_RET_REASON
MANDT [CLNT (3)]
RET_REASON [CHAR (3)]


STR_KOMG
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
KUNNR [CHAR (10)]
KDGRP [CHAR (2)]
PLTYP [CHAR (2)]
KONDA [CHAR (2)]
KONDM [CHAR (2)]
WAERK [CUKY (5)]
MATNR [CHAR (18)]
BWTAR [CHAR (10)]
CHARG [CHAR (10)]
PRODH [CHAR (18)]
MEINS [UNIT (3)]
BONUS [CHAR (2)]
PROVG [CHAR (2)]
ALAND [CHAR (3)]
WKREG [CHAR (3)]
LLAND [CHAR (3)]
REGIO [CHAR (3)]
COUNC [CHAR (3)]
CITYC [CHAR (4)]
TAXM1 [CHAR (1)]
TAXM2 [CHAR (1)]
TAXM3 [CHAR (1)]
TAXM4 [CHAR (1)]
TAXM5 [CHAR (1)]
TAXM6 [CHAR (1)]
TAXM7 [CHAR (1)]
TAXM8 [CHAR (1)]
TAXM9 [CHAR (1)]
TAXK1 [CHAR (1)]
TAXK2 [CHAR (1)]
TAXK3 [CHAR (1)]
TAXK4 [CHAR (1)]
TAXK5 [CHAR (1)]
STR_KOMG-UPMAT = MARA-MATNR
STR_KOMG-VHILM = MARA-MATNR
STR_KOMG-CHARG = MCHA-CHARG
STR_KOMG-MSR_RET_REASON = MSR_C_RET_REASON-RET_REASON
STR_KOMG-MSR_REFUND_CODE = MSR_C_RET_REFUND-RETURNS_REFUND
STR_KOMG-MANDT = T000-MANDT
STR_KOMG-BUKRS = T001-BUKRS
STR_KOMG-RESWK = T001W-WERKS
STR_KOMG-WERKS = T001W-WERKS
STR_KOMG-WERKV = T001W-WERKS
STR_KOMG-AUART = T003O-AUART
STR_KOMG-ALAND = T005-LAND1
STR_KOMG-HERKL = T005-LAND1
STR_KOMG-HLAND = T005-LAND1
STR_KOMG-LAND1 = T005-LAND1
STR_KOMG-LAND1A = T005-LAND1
STR_KOMG-LAND1Z = T005-LAND1
STR_KOMG-LANDT = T005-LAND1
STR_KOMG-LLAND = T005-LAND1
STR_KOMG-SLAND1_A = T005-LAND1
STR_KOMG-SLAND1_Z = T005-LAND1
STR_KOMG-TDLNR_LND = T005-LAND1
STR_KOMG-VERLD = T005-LAND1
STR_KOMG-COUNC = T005E-COUNC
STR_KOMG-CITYC = T005G-CITYC
STR_KOMG-J_1AREGIO = T005S-BLAND
STR_KOMG-REGIO = T005S-BLAND
STR_KOMG-REGIOA = T005S-BLAND
STR_KOMG-REGIOZ = T005S-BLAND
STR_KOMG-WKREG = T005S-BLAND
STR_KOMG-BSTME = T006-MSEHI
STR_KOMG-MEEIN = T006-MSEHI
STR_KOMG-MEINS = T006-MSEHI
MSR_C_RET_REFUND
MANDT [CLNT (3)]
RETURNS_REFUND [CHAR (3)]
T000
MANDT [CLNT (3)]
T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
T003O
CLIENT [CLNT (3)]
AUART [CHAR (4)]
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
T005E
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
COUNC [CHAR (3)]
T005G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
CITYC [CHAR (4)]
T005S
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
T016
MANDT [CLNT (3)]
BRSCH [CHAR (4)]
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]
T134
MANDT [CLNT (3)]
MTART [CHAR (4)]
T149D
MANDT [CLNT (3)]
BWTAR [CHAR (10)]
0..N
1

TAXK6 [CHAR (1)]
TAXK7 [CHAR (1)]
TAXK8 [CHAR (1)]
TAXK9 [CHAR (1)]
LIFNR [CHAR (10)]
MATKL [CHAR (9)]
EKORG [CHAR (4)]
WERKS [CHAR (4)]
RESWK [CHAR (4)]
KOLIF [CHAR (10)]
LTSNR [CHAR (6)]
WERKV [CHAR (4)]
VRKME [UNIT (3)]
GSBER [CHAR (4)]
AUART [CHAR (4)]
ZSCHL [CHAR (6)]
KOSTV [CHAR (10)]
MEEIN [UNIT (3)]
KOKRS [CHAR (4)]
KOSAR [CHAR (1)]
INFNR [CHAR (10)]
EVRTN [CHAR (10)]
EVRTP [NUMC (5)]
INCO1 [CHAR (3)]
BUKRS [CHAR (4)]
MTART [CHAR (4)]
LLIEF [CHAR (10)]
LIFRE [CHAR (10)]
BSTME [UNIT (3)]
TAXIM [CHAR (1)]
TAXIK [CHAR (1)]
TAXIW [CHAR (1)]
TXJCD [CHAR (15)]
ERKRS [CHAR (4)]
VERSI [CHAR (3)]
VERSN [CHAR (3)]
VRGAR [CHAR (1)]
FKART [CHAR (4)]
VKORGAU [CHAR (4)]
HIENR [CHAR (10)]
VARCOND [CHAR (26)]
LAND1 [CHAR (3)]
ZTERM [CHAR (4)]
GZOLX [CHAR (4)]
PWGGR [CHAR (6)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
UPMAT [CHAR (18)]
UKONM [CHAR (2)]
AUART_SD [CHAR (4)]
BUGRP [CHAR (6)]
VSTEL [CHAR (4)]
LPRIO [NUMC (2)]
LSTEL [CHAR (2)]
LADGR [CHAR (4)]
TRAGR [CHAR (4)]
MFRGR [CHAR (8)]
GARVZ [CHAR (6)]
GTART [CHAR (12)]
SHTYP [CHAR (4)]
TPLST [CHAR (4)]
VSBED [CHAR (2)]
ROUTE [CHAR (6)]
ADD01 [CHAR (10)]
ADD02 [CHAR (10)]

STR_KOMG-VRKME = T006-MSEHI
STR_KOMG-BRSCH = T016-BRSCH
STR_KOMG-MATKL = T023-MATKL
STR_KOMG-EKORG = T024E-EKORG
STR_KOMG-MTART = T134-MTART
STR_KOMG-BWTAR = T149D-BWTAR
STR_KOMG-KDGRP = T151-KDGRP
STR_KOMG-BZIRK = T171-BZIRK
STR_KOMG-VSART = T173-VSART
STR_KOMG-KONDM = T178-KONDM
STR_KOMG-UKONM = T178-KONDM
STR_KOMG-PRDHA = T179-PRODH
STR_KOMG-PRODH = T179-PRODH
STR_KOMG-KONDA = T188-KONDA
STR_KOMG-PLTYP = T189-PLTYP
STR_KOMG-COIMP = T604-STAWN
STR_KOMG-STAWN = T604-STAWN
STR_KOMG-GZOLX = T604G-GZOLX
STR_KOMG-PWGGR = T604WG-PWGGR
STR_KOMG-COADI = T610A-COADI
STR_KOMG-CASNR = T610C-CASNR
STR_KOMG-COPHA = T610D-COPHA
STR_KOMG-COKON = T610K-COKON
STR_KOMG-KTNUM = T610KP-KTPLN

T151
MANDT [CLNT (3)]
KDGRP [CHAR (2)]

T171
MANDT [CLNT (3)]
BZIRK [CHAR (6)]

T173
MANDT [CLNT (3)]
VSART [CHAR (2)]

T178
MANDT [CLNT (3)]
KONDM [CHAR (2)]

T179
MANDT [CLNT (3)]
PRODH [CHAR (18)]

T188
MANDT [CLNT (3)]
KONDA [CHAR (2)]

T189
MANDT [CLNT (3)]
PLTYP [CHAR (2)]

T604
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
STAWN [CHAR (17)]

T604G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
GZOLX [CHAR (4)]

T604WG
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
PWGGR [CHAR (6)]

T610A
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COADI [CHAR (6)]

T610C
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
CASNR [CHAR (15)]

T610D
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COPHA [CHAR (6)]

T610K
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COKON [CHAR (6)]

ADD03 [CHAR (10)]
ADD04 [CHAR (10)]
TDLNR_FA [CHAR (10)]
VHART [CHAR (4)]
VEGR1 [CHAR (5)]
VEGR2 [CHAR (5)]
VEGR3 [CHAR (5)]
VEGR4 [CHAR (5)]
VEGR5 [CHAR (5)]
VHILM [CHAR (18)]
LANDT [CHAR (3)]
VSART [CHAR (2)]
TDLNR [CHAR (10)]
TDLNR_LND [CHAR (3)]
SDABW [CHAR (4)]
SLAND1_A [CHAR (3)]
SLAND1_Z [CHAR (3)]
KNOTA [CHAR (10)]
LAND1A [CHAR (3)]
LZONEA [CHAR (10)]
REGIOA [CHAR (3)]
TRFZNA [CHAR (10)]
KNOTZ [CHAR (10)]
LAND1Z [CHAR (3)]
LZONEZ [CHAR (10)]
REGIOZ [CHAR (3)]
TRFZNZ [CHAR (10)]
SRVPOS [CHAR (18)]
BZIRK [CHAR (6)]
VKGRP [CHAR (3)]
BRSCH [CHAR (4)]
VKBUR [CHAR (4)]
PRCTR [CHAR (10)]
PPRCTR [CHAR (10)]
REP_MATNR [CHAR (18)]
LHIENR [CHAR (10)]
KDKGR [CHAR (2)]
J_1AFITP [CHAR (2)]
J_1ARFZ [CHAR (1)]
J_1AREGIO [CHAR (3)]
J_1AGICD [CHAR (2)]
J_1ADTYP [CHAR (2)]
J_1ATXREL [CHAR (10)]
VKAUS [CHAR (3)]
J_1AINDXP [CHAR (5)]
HLAND [CHAR (3)]
AUSFU [CHAR (10)]
HERKL [CHAR (3)]
VERLD [CHAR (3)]
COIMP [CHAR (17)]
STAWN [CHAR (17)]
CASNR [CHAR (15)]
EXPRF [CHAR (8)]
COKON [CHAR (6)]
COPHA [CHAR (6)]
COADI [CHAR (6)]
HERSE [CHAR (10)]
KTNUM [CHAR (10)]

0..N STR_KOMG-PLNUM = T610KP-KTPLN 0..N

T610KP
MANDT [CLNT (3)]
EILAN [CHAR (3)]
KTPLV [CHAR (2)]
KTPLN [CHAR (10)]

0..N STR_KOMG-EILGR = T610LG-EILGR 0..N

T610LG
MANDT [CLNT (3)]
EILAN [CHAR (3)]
EILGR [CHAR (10)]

0..N STR_KOMG-PREFA = T610PA-PREFA 0..N

T610PA
MANDT [CLNT (3)]
EILAN [CHAR (3)]
PREFA [CHAR (10)]

0..N STR_KOMG-EXPRF = T616-EXPRF 0..N

T616
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
EXPRF [CHAR (8)]

0..N STR_KOMG-MOGRU = T618G-MOGRU 0..N

T618G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
MOGRU [CHAR (6)]

1 STR_KOMG-KBSTAT = T686E-KBSTAT 0..N

T686E
MANDT [CLNT (3)]
KBSTAT [CHAR (2)]

0..N STR_KOMG-REP_MATNR = T8A60-REP_MATNR 1

T8A60
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
REP_MATNR [CHAR (18)]

0..N STR_KOMG-BEMOT = TBMOT-BEMOT 0..N

TBMOT
MANDT [CLNT (3)]
BEMOT [CHAR (2)]

0..N STR_KOMG-WAERK = TCURC-WAERS 0..N

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

0..N STR_KOMG-GTART = TGAR-GTART 0..N

TGAR
MANDT [CLNT (3)]
GARVZ [CHAR (6)]
GTART [CHAR (12)]

0..N STR_KOMG-GARVZ = TGAV-GARVZ 0..N

TGAV
MANDT [CLNT (3)]
GARVZ [CHAR (6)]

0..N STR_KOMG-GSBER = TGSB-GSBER 0..N

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]


PLNUM [CHAR (10)]
PREFA [CHAR (10)]
EILGR [CHAR (10)]
DELCO [CHAR (3)]
RESRC [CHAR (10)]
BEMOT [CHAR (2)]
KNUMA_AG [CHAR (10)]
KNUMA_PI [CHAR (10)]
KUNAG [CHAR (10)]
KUNWE [CHAR (10)]
KUNRG [CHAR (10)]
KUNRE [CHAR (10)]
MOGRU [CHAR (6)]
KBSTAT [CHAR (2)]
AUGRU [CHAR (3)]
BBYNR [CHAR (12)]
CNAE [CHAR (7)]
ICMSTAXPAY [CHAR (2)]
INDTYP [CHAR (2)]
TDT [CHAR (2)]
COMSIZE [CHAR (2)]
DECREGPC [CHAR (2)]
LEGALNAT [NUMC (4)]
EXTWG [CHAR (18)]
PRDHA [CHAR (18)]
MSR_RET_REASON [CHAR (3)]
MSR_REFUND_CODE [CHAR (3)]
HIER_ID [CHAR (2)]
NODE [CHAR (18)]
STR_KOMG-INCO1 = TINC-INCO1
STR_KOMG-KOKRS = TKA01-KOKRS
STR_KOMG-KOSAR = TKA05-KOSAR
STR_KOMG-ERKRS = TKEB-ERKRS
STR_KOMG-VERSI = TKVS-VERSI
STR_KOMG-VERSN = TKVS-VERSI
STR_KOMG-ZSCHL = TKZSL-ZSCHL
STR_KOMG-LADGR = TLGR-LADGR
STR_KOMG-MFRGR = TMFG-MFRGR
STR_KOMG-TAXIK = TMKK1-TAXIK
STR_KOMG-TAXIM = TMKM1-TAXIM
STR_KOMG-TAXIW = TMKW1-TAXIW
STR_KOMG-LPRIO = TPRIO-LPRIO
STR_KOMG-TAXK1 = TSKD-TAXKD
STR_KOMG-TAXK2 = TSKD-TAXKD
STR_KOMG-TAXK3 = TSKD-TAXKD
STR_KOMG-TAXK4 = TSKD-TAXKD
STR_KOMG-TAXK5 = TSKD-TAXKD
STR_KOMG-TAXK6 = TSKD-TAXKD
STR_KOMG-TAXK7 = TSKD-TAXKD
STR_KOMG-TAXK8 = TSKD-TAXKD
STR_KOMG-TAXK9 = TSKD-TAXKD
STR_KOMG-TAXM1 = TSKM-TAXKM
STR_KOMG-TAXM2 = TSKM-TAXKM
STR_KOMG-TAXM3 = TSKM-TAXKM
STR_KOMG-TAXM4 = TSKM-TAXKM
STR_KOMG-TAXM5 = TSKM-TAXKM
STR_KOMG-TAXM6 = TSKM-TAXKM
STR_KOMG-TAXM7 = TSKM-TAXKM
STR_KOMG-TAXM8 = TSKM-TAXKM
STR_KOMG-TAXM9 = TSKM-TAXKM
STR_KOMG-SPART = TSPA-SPART
TINC
MANDT [CLNT (3)]
INCO1 [CHAR (3)]
TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
TKA05
MANDT [CLNT (3)]
KOSAR [CHAR (1)]
TKEB
MANDT [CLNT (3)]
ERKRS [CHAR (4)]
TKVS
MANDT [CLNT (3)]
VERSI [CHAR (3)]
TKZSL
MANDT [CLNT (3)]
ZSCHL [CHAR (6)]
TLGR
MANDT [CLNT (3)]
LADGR [CHAR (4)]
TMFG
MANDT [CLNT (3)]
MFRGR [CHAR (8)]
TMKK1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIK [CHAR (1)]
TMKM1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIM [CHAR (1)]
TMKW1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIW [CHAR (1)]
TPRIO
MANDT [CLNT (3)]
LPRIO [NUMC (2)]
TSKD
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKD [CHAR (1)]
TSKM
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKM [CHAR (1)]
TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]


STR_KOMG-TPLST = TTDS-TPLST
TTDS
MANDT [CLNT (3)]
TPLST [CHAR (4)]
0..N
STR_KOMG-TRAGR = TTGR-TRAGR
TTGR
MANDT [CLNT (3)]
TRAGR [CHAR (4)]
0..N
STR_KOMG-TXJCD = TTXJ-TXJCD
TTXJ
MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (15)]
0..N
STR_KOMG-AUART_SD = TVAK-AUART
TVAK
MANDT [CLNT (3)]
AUART [CHAR (4)]
0..N
STR_KOMG-VARCOND = TVARC-VARCOND
TVARC
MANDT [CLNT (3)]
VARCOND [CHAR (26)]
0..N
STR_KOMG-AUGRU = TVAU-AUGRU
TVAU
MANDT [CLNT (3)]
AUGRU [CHAR (3)]
0..N
STR_KOMG-BONUS = TVBO-BONUS
TVBO
MANDT [CLNT (3)]
BONUS [CHAR (2)]
0..N
STR_KOMG-VKBUR = TVBUR-VKBUR
TVBUR
MANDT [CLNT (3)]
VKBUR [CHAR (4)]
0..N
STR_KOMG-DELCO = TVDC-DELCO
TVDC
MANDT [CLNT (3)]
DELCO [CHAR (3)]
0..N
STR_KOMG-VEGR1 = TVE1-VEGR1
TVE1
MANDT [CLNT (3)]
VEGR1 [CHAR (5)]
0..N
STR_KOMG-VEGR2 = TVE2-VEGR2
TVE2
MANDT [CLNT (3)]
VEGR2 [CHAR (5)]
0..N
STR_KOMG-VEGR3 = TVE3-VEGR3
TVE3
MANDT [CLNT (3)]
VEGR3 [CHAR (5)]
0..N
STR_KOMG-VEGR4 = TVE4-VEGR4
TVE4
MANDT [CLNT (3)]
VEGR4 [CHAR (5)]
0..N
STR_KOMG-VEGR5 = TVE5-VEGR5
TVE5
MANDT [CLNT (3)]
VEGR5 [CHAR (5)]
0..N
STR_KOMG-BUGRP = TVFBWG-BUGRP
TVFBWG
MANDT [CLNT (3)]
KAPPL [CHAR (2)]
BUGRP [CHAR (6)]
0..N
STR_KOMG-FKART = TVFK-FKART
TVFK
MANDT [CLNT (3)]
FKART [CHAR (4)]
0..N
STR_KOMG-TRFZNA = TVFTZ-TRFZN


STR_KOMG-TRFZNZ = TVFTZ-TRFZN
0..N
0..N
TVFTZ
MANDT [CLNT (3)]
TRFZN [CHAR (10)]
STR_KOMG-VRGAR = TVGA-VRGAR
0..N
TVGA
MANDT [CLNT (3)]
VRGAR [CHAR (1)]
STR_KOMG-KDKGR = TVKGG-KDKGR
0..N
TVKGG
MANDT [CLNT (3)]
KDKGR [CHAR (2)]
STR_KOMG-VKGRP = TVKGR-VKGRP
0..N
TVKGR
MANDT [CLNT (3)]
VKGRP [CHAR (3)]
STR_KOMG-KNOTA = TVKN-KNOTE
STR_KOMG-KNOTZ = TVKN-KNOTE
0..N
0..N
TVKN
MANDT [CLNT (3)]
KNOTE [CHAR (10)]
STR_KOMG-VKORG = TVKO-VKORG
STR_KOMG-VKORGAU = TVKO-VKORG
0..N
TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]
0..N
STR_KOMG-LSTEL = TVLA-LSTEL
TVLA
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
LSTEL [CHAR (2)]
0..N
STR_KOMG-VKAUS = TVLV-ABRVW
TVLV
MANDT [CLNT (3)]
ABRVW [CHAR (3)]
0..N
STR_KOMG-PROVG = TVPR-PROVG
TVPR
MANDT [CLNT (3)]
PROVG [CHAR (2)]
0..N
STR_KOMG-ROUTE = TVRO-ROUTE
TVRO
MANDT [CLNT (3)]
ROUTE [CHAR (6)]
0..N
STR_KOMG-SDABW = TVSAK-SDABW
TVSAK
MANDT [CLNT (3)]
SDABW [CHAR (4)]
0..N
STR_KOMG-VSBED = TVSB-VSBED
TVSB
MANDT [CLNT (3)]
VSBED [CHAR (2)]
0..N
STR_KOMG-VSTEL = TVST-VSTEL
TVST
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
0..N
STR_KOMG-SHTYP = TVTK-SHTYP
TVTK
MANDT [CLNT (3)]
SHTYP [CHAR (4)]
0..N
STR_KOMG-VTWEG = TVTW-VTWEG
TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]
0..N
STR_KOMG-VHART = TVTY-TRATY
TVTY
MANDT [CLNT (3)]
TRATY [CHAR (4)]
0..N
STR_KOMG-ZTERM = TVZB-ZTERM


TVZB
MANDT [CLNT (3)]
ZTERM [CHAR (4)]
STR_KOMG-EXTWG = TWEW-EXTWG
0..N
TWEW
MANDT [CLNT (3)]
EXTWG [CHAR (18)]
STR_KOMG-LZONEA = TZONE-ZONE1
0..N
TZONE
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
ZONE1 [CHAR (10)]
STR_KOMG-LZONEZ = TZONE-ZONE1
0..N
0..N
VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]
STR_KOMG-VBELN = VBUK-VBELN
0..N
VBUP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
STR_KOMG-POSNR = VBUP-POSNR
0..N
VTADD01
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
STR_KOMG-ADD01 = VTADD01-ADD_INFO
0..N
VTADD02
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
STR_KOMG-ADD02 = VTADD02-ADD_INFO
0..N
VTADD03
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
STR_KOMG-ADD03 = VTADD03-ADD_INFO
0..N
VTADD04
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
STR_KOMG-ADD04 = VTADD04-ADD_INFO
0..N
WRF_MATGRP_HIER
MANDT [CLNT (3)]
HIER_ID [CHAR (2)]
STR_KOMG-HIER_ID = WRF_MATGRP_HIER-HIER_ID
0..N
WRF_MATGRP_STRUC
MANDT [CLNT (3)]
HIER_ID [CHAR (2)]
NODE [CHAR (18)]
DATE_FROM [DATS (8)]
STR_KOMG-NODE = WRF_MATGRP_STRUC-NODE
0..N
WYT1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
LTSNR [CHAR (6)]
STR_KOMG-LTSNR = WYT1-LTSNR
0..N