SAP ABAP table U_16991 {Generated Table for View}


U_16991-J_1BBRANCH = J_1BBRANCH-BRANCH
0..N
J_1BBRANCH
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
BRANCH [CHAR (4)]
U_16991-KUNNR = KNA1-KUNNR
0..N
KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]
U_16991-NODETYPE = MDRP_NODT-NODETYPE
0..N
MDRP_NODT
NODETYPE [CHAR (3)]
U_16991-MANDT = T000-MANDT
0..N
T000
MANDT [CLNT (3)]
U_16991-BWKEY = T001K-BWKEY
0..N
T001K
MANDT [CLNT (3)]
BWKEY [CHAR (4)]
U_16991-SPRAS = T002-SPRAS
0..N
T002
SPRAS [LANG (1)]
U_16991-LAND1 = T005-LAND1
0..N
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
U_16991-COUNC = T005E-COUNC
0..N
T005E
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
COUNC [CHAR (3)]
U_16991-CITYC = T005G-CITYC
0..N
T005G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
CITYC [CHAR (4)]
U_16991-REGIO = T005S-BLAND
0..N
T005S
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]
U_16991-EKORG = T024E-EKORG
1..N
T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]
U_16991-FABKL = TFACD-IDENT
0..N
TFACD
IDENT [CHAR (2)]
U_16991-AWSLS = TKV01-AWSLS
0..N
TKV01
MANDT [CLNT (3)]
AWOBA [CHAR (2)]
AWSLS [CHAR (6)]
U_16991-TAXIW = TMKW1-TAXIW
0..N
TMKW1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIW [CHAR (1)]
U_16991-TXJCD = TTXJ-TXJCD
0..N
TTXJ
MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (15)]
U_16991-FPRFW = TWFPF-FPRFW
0..N
TWFPF
MANDT [CLNT (3)]
FPRFW [CHAR (3)]
U_16991-ZONE1 = TZONE-ZONE1
0..N
TZONE
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
ZONE1 [CHAR (10)]
U_16991
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BWKEY [CHAR (4)]
FABKL [CHAR (2)]
LAND1 [CHAR (3)]
SPRAS [LANG (1)]
REGIO [CHAR (3)]
COUNC [CHAR (3)]
CITYC [CHAR (4)]
TXJCD [CHAR (15)]
AWSLS [CHAR (6)]
TAXIW [CHAR (1)]
J_1BBRANCH [CHAR (4)]
FPRFW [CHAR (3)]
NODETYPE [CHAR (3)]
EKORG [CHAR (4)]
KUNNR [CHAR (10)]
ZONE1 [CHAR (10)]
1
{0,1}
1
{0,1}
1
{0,1}