SAP ABAP table V_IVP_OR {Generated Table for View}

V_IVP_OR
MANDT [CLNT (3)]
PRNAM [CHAR (8)]
GJAHR [NUMC (4)]
POSNR [NUMC (8)]
POSID [CHAR (24)]
AUFNR [CHAR (12)]
AUART [CHAR (4)]
REFNR [CHAR (12)]
BUKRS [CHAR (4)]
WERKS [CHAR (4)]
GSBER [CHAR (4)]
KOKRS [CHAR (4)]
KOSTV [CHAR (10)]
STORT [CHAR (10)]
SOWRK [CHAR (4)]
WAERS [CUKY (5)]
ESTNR [NUMC (2)]
VOGRP [CHAR (4)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KALSM [CHAR (6)]
ABKRS [NUMC (2)]
KSTAR [CHAR (10)]
KOSTL [CHAR (10)]
SAKNR [CHAR (10)]
CYCLE [CHAR (10)]
OBJNR [CHAR (22)]
PRCTR [CHAR (10)]
PSPEL [NUMC (8)]
AWSLS [CHAR (6)]
ABGSL [CHAR (6)]
TXJCD [CHAR (15)]
FUNC_AREA [CHAR (16)]
KDAUF [CHAR (10)]
IVPRO [CHAR (6)]
LOGSYSTEM [CHAR (10)]
ABUKR [CHAR (4)]
AKSTL [CHAR (10)]
SIZECL [CHAR (2)]
IZWEK [CHAR (2)]
UMWKZ [CHAR (5)]
ZSCHM [CHAR (7)]
ANFAUFNR [CHAR (12)]
BEMOT [CHAR (2)]
VERAA_USER [CHAR (12)]
VNAME [CHAR (6)]
RECID [CHAR (2)]
ETYPE [CHAR (3)]
JV_JIBCL [CHAR (3)]
JV_JIBSA [CHAR (5)]
FERC_IND [CHAR (4)]

V_IVP_OR-ANFAUFNR = AUFK-AUFNR {0..N} — **AUFK** [MANDT (CLNT (3)), AUFNR (CHAR (12))]

V_IVP_OR-REFNR = AUFK-AUFNR {0..N} — **CEPC** [MANDT (CLNT (3)), PRCTR (CHAR (10)), DATBI (DATS (8)), KOKRS (CHAR (4))]

V_IVP_OR-PRCTR = CEPC-PRCTR {0..N}

V_IVP_OR-KSTAR = CSKB-KSTAR {0..N} — **CSKB** [MANDT (CLNT (3)), KOKRS (CHAR (4)), KSTAR (CHAR (10)), DATBI (DATS (8))]

V_IVP_OR-AKSTL = CSKS-KOSTL {0..N} — **CSKS** [MANDT (CLNT (3)), KOKRS (CHAR (4)), KOSTL (CHAR (10)), DATBI (DATS (8))]

V_IVP_OR-CYCLE = CSKS-KOSTL {0..N}

V_IVP_OR-KOSTL = CSKS-KOSTL {0..N}

V_IVP_OR-KOSTV = CSKS-KOSTL {0..N}

V_IVP_OR-FERC_IND = FERC_C7-IND {0..N} — **FERC_C7** [MANDT (CLNT (3)), IND (CHAR (4))]

V_IVP_OR-PRNAM = IMTP-PRNAM {0..N} — **IMTP** [MANDT (CLNT (3)), PRNAM (CHAR (8)), GJAHR (NUMC (4))]

V_IVP_OR-OBJNR = ONR00-OBJNR {1} — **ONR00** [MANDT (CLNT (3)), OBJNR (CHAR (22))]

V_IVP_OR-PSPEL = PRPS-PSPNR {0..N} — **PRPS** [MANDT (CLNT (3)), PSPNR (NUMC (8))]

V_IVP_OR-SAKNR = SKB1-SAKNR {0..N} — **SKB1** [MANDT (CLNT (3)), BUKRS (CHAR (4)), SAKNR (CHAR (10))]

V_IVP_OR-MANDT = T000-MANDT {0..N} — **T000** [MANDT (CLNT (3))]

V_IVP_OR-ABUKR = T001-BUKRS {0..N} — **T001** [MANDT (CLNT (3)), BUKRS (CHAR (4))]

V_IVP_OR-BUKRS = T001-BUKRS {0..N}

V_IVP_OR-SOWRK = T001W-WERKS {0..N} — **T001W** [MANDT (CLNT (3)), WERKS (CHAR (4))]

V_IVP_OR-WERKS = T001W-WERKS {0..N}

V_IVP_OR-AUART = T003O-AUART {0..N} — **T003O** [CLIENT (CLNT (3)), AUART (CHAR (4))]

V_IVP_OR-IZWEK = T087I-IZWEK {0..N} — **T087I** [MANDT (CLNT (3)), IZWEK (CHAR (2))]

V_IVP_OR-UMWKZ = T087K-UMWKZ {0..N} — **T087K** [MANDT (CLNT (3)), UMWKZ (CHAR (5))]

V_IVP_OR-STORT = T499S-STAND {0..N} — **T499S** [MANDT (CLNT (3)), WERKS (CHAR (4)), STAND (CHAR (10))]

V_IVP_OR-KAPPL = T681A-KAPPL {0..N} — **T681A** [KAPPL (CHAR (2))]

V_IVP_OR-KVEWE = T681V-KVEWE {0..N} — **T681V** [KVEWE (CHAR (1))]

V_IVP_OR-KALSM = T683-KALSM {0..N} — **T683** [MANDT (CLNT (3)), KVEWE (CHAR (1)), KAPPL (CHAR (2)), KALSM (CHAR (6))]

V_IVP_OR-JV_JIBCL = T8J6A-CLASS {0..N} — **T8J6A** [MANDT (CLNT (3)), BUKRS (CHAR (4)), CLASS (CHAR (3))]

V_IVP_OR-JV_JIBSA = T8J6C-SUBCLASS {0..N} — **T8J6C** [MANDT (CLNT (3)), BUKRS (CHAR (4)), CLASS (CHAR (3)), SUBCLASS (CHAR (5))]

V_IVP_OR-ETYPE = T8JG-ETYPE {0..N} — **T8JG** [MANDT (CLNT (3)), BUKRS (CHAR (4)), VNAME (CHAR (6)), ETYPE (CHAR (3)), EDATE (NUMC (8))]

V_IVP_OR-RECID = T8JJ-RECID {0..N} — **T8JJ** [MANDT (CLNT (3)), BUKRS (CHAR (4)), RECID (CHAR (2))]

V_IVP_OR-VNAME = T8JV-VNAME {0..N} — **T8JV** [MANDT (CLNT (3)), BUKRS (CHAR (4)), VNAME (CHAR (6))]

V_IVP_OR-SIZECL = TAIF5-SIZECL {0..N} — **TAIF5** [MANDT (CLNT (3)), SIZECL (CHAR (2))]

V_IVP_OR-IVPRO = TAPRF-IVPRO {0..N} — **TAPRF** [MANDT (CLNT (3)), IVPRO (CHAR (6))]

V_IVP_OR-LOGSYSTEM = TBDLS-LOGSYS {0..N} — **TBDLS** [LOGSYS (CHAR (10))]

V_IVP_OR-BEMOT = TBMOT-BEMOT {0..N} — **TBMOT** [MANDT (CLNT (3)), BEMOT (CHAR (2))]

V_IVP_OR-WAERS = TCURC-WAERS {0..N} — **TCURC** [MANDT (CLNT (3)), WAERS (CUKY (5))]

V_IVP_OR-FUNC_AREA = TFKB-FKBER {0..N} — **TFKB** [MANDT (CLNT (3)), FKBER (CHAR (16))]

V_IVP_OR-GSBER = TGSB-GSBER {0..N} — **TGSB** [MANDT (CLNT (3)), GSBER (CHAR (4))]

V_IVP_OR-KOKRS = TKA01-KOKRS {0..N} — **TKA01** [MANDT (CLNT (3)), KOKRS (CHAR (4))]

V_IVP_OR-VOGRP = TKAVG-GRUPPE {0..N} — **TKAVG** [MANDT (CLNT (3)), OBJID (CHAR (1)), GRUPPE (CHAR (4)), ACTIVITY (CHAR (4))]

V_IVP_OR-ABGSL = TKKAA-ABGSL {0..N} — **TKKAA** [MANDT (CLNT (3)), ABGSL (CHAR (6))]

V_IVP_OR-ESTNR = TKO03-ASTNR {0..N} — **TKO03** [CLIENT (CLNT (3)), ART (CHAR (4)), ASTNR (NUMC (2))]

V_IVP_OR-ABKRS = TKO08-ABKRS {0..N} — **TKO08** [CLIENT (CLNT (3)), KOKRS (CHAR (4)), ABKRS (NUMC (2))]

V_IVP_OR-AWSLS = TKV01-AWSLS {0..N} — **TKV01** [MANDT (CLNT (3)), AWOBA (CHAR (2)), AWSLS (CHAR (6))]

V_IVP_OR-ZSCHM = TPI01-ZSCHM {0..N} — **TPI01** [MANDT (CLNT (3)), ZSCHM (CHAR (7))]

V_IVP_OR-TXJCD = TTXJ-TXJCD {0..N} — **TTXJ** [MANDT (CLNT (3)), KALSM (CHAR (6)), TXJCD (CHAR (15))]

V_IVP_OR-VERAA_USER = USR02-BNAME {0..N} — **USR02** [MANDT (CLNT (3)), BNAME (CHAR (12))]

V_IVP_OR-KDAUF = VBUK-VBELN {0..N} — **VBUK** [MANDT (CLNT (3)), VBELN (CHAR (10))]