SAP ABAP table VIAUFKST {Generated Table for View}


VIAUFKST.ADBNR_ILOA = ADRC-ADDRNUMBER
0..N
ADRC
CLIENT CLNT (3)
ADDRNUMBER [CHAR (10)]
DATE_FROM [DATS (8)]
NATION [CHAR (1)]
VIAUFKST.PRENR = AENR-AENNR
0..N
AENR
MANDT [CLNT (3)]
AENNR [CHAR (12)]
VIAUFKST.AUFNR = AUFK-AUFNR
0..N
AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]
VIAUFKST.DAUFN = AUFK-AUFNR
0..N
VIAUFKST.AUFNR = AUFK-AUFNR
VIAUFKST.STLEAD_AUFNR = AUFK-AUFNR
VIAUFKST.REFNR = AUFK-AUFNR
CEPC
MANDT [CLNT (3)]
PRCTR [CHAR (10)]
DATBI [DATS (8)]
KOKRS [CHAR (4)]
VIAUFKST.PRCTR = CEPC-PRCTR
0..N
VIAUFKST.GEWRK = CRID-OBJID
0..N
CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]
VIAUFKST.PPSID = CRID-OBJID
VIAUFKST.KSTAR = CSKS-KSTAR
0..N
CSKB
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KSTAR [CHAR (10)]
DATBI [DATS (8)]
VIAUFKST.CYCLE = CSKS-KOSTL
0..N
CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]
VIAUFKST.KOSTV = CSKS-KOSTL
VIAUFKST.EQUNR = EQUI-EQUNR
0..N
EQUI
MANDT [CLNT (3)]
EQUNR [CHAR (18)]
VIAUFKST.FERC_IND = FERC_C7-IND
FERC_C7
MANDT [CLNT (3)]
IND [CHAR (4)]
VIAUFKST.PTLNR = IFLOT-PTLNR
0..N
IFLOT
MANDT [CLNT (3)]
PTLNR [CHAR (10)]
VIAUFKST.ILOAN = ILOA-ILOAN
0..N
ILOA
MANDT [CLNT (3)]
ILOAN [CHAR (12)]
VIAUFKST.KUNUM = KNA1-KUNNR
0..N
KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]
VIAUFKST.BAUTL = MARA-MATNR
0..N
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
VIAUFKST.PUBREF = MARA-MATNR
VIAUFKST.SERMAT = MARA-MATNR
VIAUFKST.STLBEZ = MARA-MATNR
MPLA
MANDT [CLNT (3)]
WARPL [CHAR (12)]
VIAUFKST.WARPL = MPLA-WARPL
0..N
ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]
VIAUFKST.OBJNR = ONR00-OBJNR
VIAUFKST.PRONR = PRPS-PSPNR
0..N
PROJ
MANDT [CLNT (3)]
PSPNR [NUMC (8)]
VIAUFKST.PROID = PRPS-PSPNR
0..N
PRPS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]
VIAUFKST.PSPEL = PRPS-PSPNR
0..N
QMEL
MANDT [CLNT (3)]
QMNUM [CHAR (12)]
VIAUFKST.QMNUM = QMEL-QMNUM
0..N
SER00
MANDT [CLNT (3)]
OBKNR [INT4 (10)]
VIAUFKST.OBKNR = SER00-OBKNR
0..N
SKB1
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
SAKNR [CHAR (10)]
VIAUFKST.SAKNR = SKB1-SAKNR
0..N
T000
MANDT [CLNT (3)]
VIAUFKST.MANDT = T000-MANDT
0..N
T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VIAUFKST.BUKRS = T001-BUKRS
0..N
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
VIAUFKST.SOWRK = T001W-WERKS
0..N
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
VIAUFKST.WERKS = T001W-WERKS
VIAUFKST.WERKS = T001W-WERKS
T003O
MANDT [CLNT (3)]
AUART [CHAR (4)]
VIAUFKST.AUART = T003O-AUART
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
VIAUFKST.GMEIN = T006-MSEHI
0..N
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
VIAUFKST.MEINS = T006-MSEHI
VIAUFKST.PFEIN = T006-MSEHI
T024A
MANDT [CLNT (3)]
EKGRP [CHAR (3)]
VIAUFKST.EKGRP = T024A-EFVOR
0..N
T024D
MANDT [CLNT (3)]
WERKS [CHAR (4)]
DISPO [CHAR (3)]
VIAUFKST.PLGRP = T024A-EFVOR
VIAUFKST.DISPO = T024D-DISPO
VIAUFKST.EFVOR = T024F-EFVOR
T024F
MANDT [CLNT (3)]
INGRP [CHAR (3)]
EFVOR [CHAR (3)]
VIAUFKST.INGRP = T024I-INGRP
T024I
MANDT [CLNT (3)]
INGRP [CHAR (3)]
VIAUFKST.REVNR = T352R-REVNR
T352R
MANDT [CLNT (3)]
REVNR [CHAR (6)]
VIAUFKST.ILART = T353I-ILART
T353I
MANDT [CLNT (3)]
ILART [CHAR (3)]
VIAUFKST.PRIOK = T356-PRIOK
T356
MANDT [CLNT (3)]
ARTPR [CHAR (2)]
VIAUFKST.ARTPR = T356A-ARTPR
T356A
MANDT [CLNT (3)]
ARTPR [CHAR (2)]
VIAUFKST.BEBER = T357-BEBER
T357
MANDT [CLNT (3)]
BEBER [CHAR (3)]
VIAUFKST.ANLZU = T357M-ANLZU
T357M
MANDT [CLNT (3)]
ANLZU [CHAR (1)]
VIAUFKST.ABCKZ = T370C-ABCKZ
T370C
MANDT [CLNT (3)]
ABCKZ [CHAR (1)]
VIAUFKST.IWERK = T399I-IWERK
T399I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
VIAUFKST.PVERW = T411-VERWE
T411
MANDT [CLNT (3)]
VERWE [CHAR (3)]
VIAUFKST.STLST = T415S-STLST
T415S
MANDT [CLNT (3)]
STLST [NUMC (2)]
VIAUFKST.STLAN = T416-STLAN
T416
MANDT [CLNT (3)]
STLAN [CHAR (1)]
VIAUFKST.FHORI = T436A-FHORI
T436A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FHORI [CHAR (3)]
VIAUFKST.TERMZ = T682-TERMKZ
T682
MANDT [CLNT (3)]
TERMKZ [CHAR (1)]
VIAUFKST.STORT = T499S-STAND
T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]
VIAUFKST.KAPPL = T681A-KAPPL
T681A
MANDT [CLNT (3)]
KAPPL [CHAR (2)]
VIAUFKST.KVEWE = T681V-KVEWE
T681V
MANDT [CLNT (3)]
KVEWE [CHAR (1)]
VIAUFKST.KALSM = T683-KALSM
T683
MANDT [CLNT (3)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KALSM [CHAR (6)]
VIAUFKST.ZV_JIBCL = TBJSA-CLASS
TBJSA
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
CLASS [CHAR (18)]
VIAUFKST.ZV_JIBSA = TBJSC-SUBCLASS
TBJSC
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
CLASS [CHAR (18)]
SUBCLASS [CHAR (5)]
VIAUFKST.ETYPE = TBJG-ETYPE
TBJG
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VNAME [CHAR (6)]
ETYPE [CHAR (3)]
TGBTE [NUMC (8)]
VIAUFKST.RECID = TBJI-RECID
TBJI
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VNAME [CHAR (6)]
RECID [CHAR (2)]
TBJV
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VNAME [CHAR (6)]
VIAUFKST.BEMOT = TBMOT-BEMOT
TBMOT
MANDT [CLNT (3)]
BEMOT [CHAR (2)]
VIAUFKST.PLNAW = TCA09-PLNAW
TCA09
MANDT [CLNT (3)]
PLNAW [CHAR (11)]
VIAUFKST.PROFID = TCN41-PROFIDNETZ
TCN41
MANDT [CLNT (3)]
PLNAW [CHAR (11)]
PROFIDNETZ [CHAR (75)]
VIAUFKST.WAERS = TCURC-WAERS
TCURC
MANDT [CLNT (3)]
WAERS [CLNT (5)]
VIAUFKST.GSBER = TGSB-GSBER
TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]
VIAUFKST.KOKRS = TKA01-KOKRS
TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
VIAUFKST.VGGRP = TKAVG-GRUPPE
TKAVG
MANDT [CLNT (3)]
GBOZ [CHAR (1)]
GRUPPE [CHAR (4)]
ACTIVITY [CHAR (4)]
VIAUFKST.ABGSL = TKKAA-ABGSL
TKKAA
MANDT [CLNT (3)]
ABGSL [CHAR (6)]
VIAUFKST.ESTNR = TKO03-ASTNR
TKO03
CLIENT [CLNT (3)]
ART [CHAR (4)]
ASTNR [NUMC (2)]
VIAUFKST.ABKRS = TKO08-ABKRS
TKO08
CLIENT [CLNT (3)]
KOKRS [CHAR (4)]
ABKRS [NUMC (2)]
VIAUFKST.AWSLS = TKV01-AWSLS
TKV01
MANDT [CLNT (3)]
AWGRA [CHAR (2)]
AWSLS [CHAR (6)]
VIAUFKST.SCREENTY = TQ87-SCREENTY
TQ87
SCREENTY [CHAR (4)]
VIAUFKST.VKORG = TVKO-VKORG
TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VIAUFKST.VTWEG = TVKOV-VTWEG
TVKOV
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
VIAUFKST.SPART = TVTA-SPART
TVTA
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
VIAUFKST.VERAA_USER = USR02-BNAME
USR02
MANDT [CLNT (3)]
BNAME [CHAR (12)]
VIAUFKST.KDAUF = VBUK-VBELN
VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]
VIAUFKST
MANDT [CLNT (3)]
AUFNR [CHAR (12)]
ADRNR [CHAR (10)]
ADRNR_LOADING [CHAR (10)]
PRNOR [CHAR (1)]
EQUNR [CHAR (18)]
BAUTL [CHAR (18)]
ILOAN [CHAR (12)]
ANLZU [CHAR (1)]
AWERK [CHAR (4)]
INGRP [CHAR (3)]
KNDEP [CHAR (3)]
GEWRK [NUMC (8)]
KUNUM [CHAR (10)]
GASUN [UNIT (3)]
WAPRL [CHAR (12)]
LAUFN [CHAR (12)]
OBKNR [INT4 (10)]
REVNR [CHAR (6)]
LART [CHAR (3)]
QMNUM [CHAR (12)]
SERMAT [CHAR (18)]
SCREENTY [CHAR (4)]
AUART [CHAR (4)]
AEFNR [CHAR (12)]
BUKRS [CHAR (4)]
WERKS [CHAR (4)]
PLGRP [CHAR (3)]
ADRS [CHAR (2)]
KDSTY [CHAR (1)]
SOWRK [CHAR (4)]
WAERS [CLNT (5)]
ESTNR [NUMC (2)]
VGGRP [CHAR (4)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KALSM [CHAR (6)]
ABKRS [NUMC (2)]
KSTAR [CHAR (10)]
SAKNR [CHAR (10)]
CYCLE [CHAR (10)]
OBJNR [CHAR (22)]
PRCTR [CHAR (10)]
PSPEL [NUMC (8)]
ANSLS [CHAR (6)]
ABGSL [CHAR (6)]
KDGLP [CHAR (10)]
BEMOT [CHAR (2)]
VERAA_USER [CHAR (12)]
VNAME [CHAR (6)]
RECID [CHAR (2)]
ETYPE [CHAR (3)]
ZV_JIBCL [CHAR (30)]
ZV_JIBSA [CHAR (5)]
FERC_IND [CHAR (4)]
STORT [CHAR (10)]
TPLNR [CHAR (30)]
ABCKZ [CHAR (1)]
IWERK [CHAR (4)]
BEBER [CHAR (3)]
PRIOK [NUMC (2)]
PRIOID [NUMC (8)]
DAUFN [CHAR (12)]
GMEIN [UNIT (3)]
PLANNZ [CHAR (18)]
PLANP [CHAR (11)]
PVERW [CHAR (3)]
PLANW [UNIT (3)]
PFEIN [UNIT (3)]
STLST [NUMC (2)]
SMINPY [UNIT (3)]
SAENR [CHAR (12)]
STLAN [CHAR (1)]
ZASKI [CHAR (12)]
FEVOR [CHAR (3)]
FHORI [CHAR (3)]
TERMZ [CHAR (1)]
PROFID [CHAR (75)]
PRNNR [NUMC (8)]
ZASC_AUFNR [CHAR (12)]
VNDRG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
ADRNR_LOADING [CHAR (10)]
(0,1) VTSBUS
VIAUFKST
MANDT [CLNT (3)]
AUFNR [CHAR (12)]
(0,1)
(0,1)
(0,1)
(0,1)
1
1
(0,1)
(0,1)
(0,1)
(0,1)