SAP ABAP table WB2_KEY_CHANGE {New condition keys}




WB2_KEY_CHANGE-CNAE_KG_KG = J_1BTCNAE-J_1BCNAE
J_1BTCNAE
MANDT [CLNT (3)]
J_1BCNAE [CHAR (7)]
WB2_KEY_CHANGE-COMSIZE_KG_KG = J_1BTCOMSIZE-J_1BCOMSIZE
J_1BTCOMSIZE
MANDT [CLNT (3)]
J_1BCOMSIZE [CHAR (2)]
WB2_KEY_CHANGE-DECREGPC_KG_KG = J_1BTDECREGPC-J_1BDECREGPC
J_1BTDECREGPC
MANDT [CLNT (3)]
J_1BDECREGPC [CHAR (2)]
WB2_KEY_CHANGE-ICMSTAXPAY_KG_KG = J_1BTICMSTAXPAY-J_1BICMSTAXPAY
J_1BTICMSTAXPAY
MANDT [CLNT (3)]
J_1BICMSTAXPAY [CHAR (2)]
WB2_KEY_CHANGE-INDTYP_KG_KG = J_1BTINDTYP-J_1BINDTYP
J_1BTINDTYP
MANDT [CLNT (3)]
J_1BINDTYP [CHAR (2)]
WB2_KEY_CHANGE-LEGALNAT_KG_KG = J_1BTLEGALNAT-J_1BLEGALNAT
J_1BTLEGALNAT
MANDT [CLNT (3)]
J_1BLEGALNAT [NUMC (4)]
WB2_KEY_CHANGE-TDT_KG_KG = J_1BTTDT-J_1BTDT
J_1BTTDT
MANDT [CLNT (3)]
J_1BTDT [CHAR (2)]
WB2_KEY_CHANGE-HIENR_KG_KG = KNA1-KUNNR
WB2_KEY_CHANGE-KUNAG_KG_KG = KNA1-KUNNR
WB2_KEY_CHANGE-KUNNR_KG_KG = KNA1-KUNNR
WB2_KEY_CHANGE-KUNRE_KG_KG = KNA1-KUNNR
WB2_KEY_CHANGE-KUNRG_KG_KG = KNA1-KUNNR
WB2_KEY_CHANGE-KUNWE_KG_KG = KNA1-KUNNR
KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]
WB2_KEY_CHANGE-KNUMA_AG_KG_KG = KONA-KNUMA
WB2_KEY_CHANGE-KNUMA_AG_KH = KONA-KNUMA
WB2_KEY_CHANGE-KNUMA_BO_KH = KONA-KNUMA
WB2_KEY_CHANGE-KNUMA_PI_KG_KG = KONA-KNUMA
WB2_KEY_CHANGE-KNUMA_PI_KH = KONA-KNUMA
WB2_KEY_CHANGE-KNUMA_SD_KH = KONA-KNUMA
WB2_KEY_CHANGE-KNUMA_SQ_KH = KONA-KNUMA
KONA
MANDT [CLNT (3)]
KNUMA [CHAR (10)]
WB2_KEY_CHANGE-BBYNR_KG_KG = KONBBYH-BBYNR
KONBBYH
MANDT [CLNT (3)]
BBYNR [CHAR (12)]
WB2_KEY_CHANGE-AUSFU_KG_KG = LFA1-LIFNR
WB2_KEY_CHANGE-HERSE_KG_KG = LFA1-LIFNR
WB2_KEY_CHANGE-KOLIF_KG_KG = LFA1-LIFNR
WB2_KEY_CHANGE-LHIENR_KG_KG = LFA1-LIFNR
WB2_KEY_CHANGE-LIFNR_KG_KG = LFA1-LIFNR
WB2_KEY_CHANGE-LIFRE_KG_KG = LFA1-LIFNR
WB2_KEY_CHANGE-LLIEF_KG_KG = LFA1-LIFNR
WB2_KEY_CHANGE-TDLNR_FA_KG_KG = LFA1-LIFNR
WB2_KEY_CHANGE-TDLNR_KG_KG = LFA1-LIFNR
LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
WB2_KEY_CHANGE-MATNR_KG_KG = MARA-MATNR
WB2_KEY_CHANGE-UPMAT_KG_KG = MARA-MATNR
WB2_KEY_CHANGE-VHILM_KG_KG = MARA-MATNR
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WB2_KEY_CHANGE-CHARG_KG_KG = MCHA-CHARG
MCHA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
CHARG [CHAR (10)]
MSR_C_RET_REASON
MANDT [CLNT (3)]
RET_REASON [CHAR (3)]
MSR_C_RET_REFUND
MANDT [CLNT (3)]
RETURNS_REFUND [CHAR (3)]
T000
MANDT [CLNT (3)]
T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
0..N


WB2_KEY_CHANGE
MANDT_KG_KG [CLNT (3)]
VKORG_KG_KG [CHAR (4)]
VTWEG_KG_KG [CHAR (2)]
SPART_KG_KG [CHAR (2)]
KUNNR_KG_KG [CHAR (10)]
KDGRP_KG_KG [CHAR (2)]
PLTYP_KG_KG [CHAR (2)]
KONDA_KG_KG [CHAR (2)]
KONDM_KG_KG [CHAR (2)]
WAERK_KG_KG [CUKY (5)]
MATNR_KG_KG [CHAR (18)]
BWTAR_KG_KG [CHAR (10)]
CHARG_KG_KG [CHAR (10)]
PRODH_KG_KG [CHAR (18)]
MEINS_KG_KG [UNIT (3)]
BONUS_KG_KG [CHAR (2)]
PROVG_KG_KG [CHAR (2)]
ALAND_KG_KG [CHAR (3)]
WKREG_KG_KG [CHAR (3)]
LLAND_KG_KG [CHAR (3)]
REGIO_KG_KG [CHAR (3)]
COUNC_KG_KG [CHAR (3)]
CITYC_KG_KG [CHAR (4)]
TAXM1_KG_KG [CHAR (1)]
TAXM2_KG_KG [CHAR (1)]
TAXM3_KG_KG [CHAR (1)]
TAXM4_KG_KG [CHAR (1)]
TAXM5_KG_KG [CHAR (1)]
TAXM6_KG_KG [CHAR (1)]
TAXM7_KG_KG [CHAR (1)]
TAXM8_KG_KG [CHAR (1)]
TAXM9_KG_KG [CHAR (1)]
TAXK1_KG_KG [CHAR (1)]
TAXK2_KG_KG [CHAR (1)]
TAXK3_KG_KG [CHAR (1)]
TAXK4_KG_KG [CHAR (1)]
TAXK5_KG_KG [CHAR (1)]
TAXK6_KG_KG [CHAR (1)]
TAXK7_KG_KG [CHAR (1)]
TAXK8_KG_KG [CHAR (1)]
TAXK9_KG_KG [CHAR (1)]
LIFNR_KG_KG [CHAR (10)]
MATKL_KG_KG [CHAR (9)]
EKORG_KG_KG [CHAR (4)]
WERKS_KG_KG [CHAR (4)]
RESWK_KG_KG [CHAR (4)]
KOLIF_KG_KG [CHAR (10)]
LTSNR_KG_KG [CHAR (6)]
WERKV_KG_KG [CHAR (4)]
VRKME_KG_KG [UNIT (3)]
GSBER_KG_KG [CHAR (4)]
AUART_KG_KG [CHAR (4)]
ZSCHL_KG_KG [CHAR (6)]
KOSTV_KG_KG [CHAR (10)]
MEEIN_KG_KG [UNIT (3)]
KOKRS_KG_KG [CHAR (4)]
WB2_KEY_CHANGE-MSR_RET_REASON_KG_KG = MSR_C_RET_REASON-RET_REASON
WB2_KEY_CHANGE-MSR_REFUND_CODE_KG_KG = MSR_C_RET_REFUND-RETURNS_REFUND
WB2_KEY_CHANGE-MANDT_KG_KG = T000-MANDT
WB2_KEY_CHANGE-MANDT_KH = T000-MANDT
WB2_KEY_CHANGE-BUKRS_KG_KG = T001-BUKRS
WB2_KEY_CHANGE-RESWK_KG_KG = T001W-WERKS
WB2_KEY_CHANGE-WERKS_KG_KG = T001W-WERKS
WB2_KEY_CHANGE-WERKV_KG_KG = T001W-WERKS
WB2_KEY_CHANGE-AUART_KG_KG = T003O-AUART
WB2_KEY_CHANGE-ALAND_KG_KG = T005-LAND1
WB2_KEY_CHANGE-HERKL_KG_KG = T005-LAND1
WB2_KEY_CHANGE-HLAND_KG_KG = T005-LAND1
WB2_KEY_CHANGE-LAND1A_KG_KG = T005-LAND1
WB2_KEY_CHANGE-LAND1Z_KG_KG = T005-LAND1
WB2_KEY_CHANGE-LAND1_KG_KG = T005-LAND1
WB2_KEY_CHANGE-LANDT_KG_KG = T005-LAND1
WB2_KEY_CHANGE-LLAND_KG_KG = T005-LAND1
WB2_KEY_CHANGE-SLAND1_A_KG_KG = T005-LAND1
WB2_KEY_CHANGE-SLAND1_Z_KG_KG = T005-LAND1
WB2_KEY_CHANGE-TDLNR_LND_KG_KG = T005-LAND1
WB2_KEY_CHANGE-VERLD_KG_KG = T005-LAND1
WB2_KEY_CHANGE-COUNC_KG_KG = T005E-COUNC
WB2_KEY_CHANGE-CITYC_KG_KG = T005G-CITYC
WB2_KEY_CHANGE-J_1AREGIO_KG_KG = T005S-BLAND
WB2_KEY_CHANGE-REGIOA_KG_KG = T005S-BLAND
WB2_KEY_CHANGE-REGIOZ_KG_KG = T005S-BLAND
WB2_KEY_CHANGE-REGIO_KG_KG = T005S-BLAND
WB2_KEY_CHANGE-WKREG_KG_KG = T005S-BLAND
WB2_KEY_CHANGE-BSTME_KG_KG = T006-MSEHI
WB2_KEY_CHANGE-MEEIN_KG_KG = T006-MSEHI
WB2_KEY_CHANGE-MEINS_KG_KG = T006-MSEHI
WB2_KEY_CHANGE-VRKME_KG_KG = T006-MSEHI
WB2_KEY_CHANGE-BRSCH_KG_KG = T016-BRSCH
T003O
CLIENT [CLNT (3)]
AUART [CHAR (4)]
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
T005E
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
COUNC [CHAR (3)]
T005G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
CITYC [CHAR (4)]
T005S
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
T016
MANDT [CLNT (3)]
BRSCH [CHAR (4)]
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]
T134
MANDT [CLNT (3)]
MTART [CHAR (4)]
T149D
MANDT [CLNT (3)]
BWTAR [CHAR (10)]
T151
MANDT [CLNT (3)]
KDGRP [CHAR (2)]
T171
MANDT [CLNT (3)]
BZIRK [CHAR (6)]
T173
MANDT [CLNT (3)]
VSART [CHAR (2)]
T178
MANDT [CLNT (3)]
KONDM [CHAR (2)]

KOSAR_KG_KG [CHAR (1)]
INFNR_KG_KG [CHAR (10)]
EVRTN_KG_KG [CHAR (10)]
EVRTP_KG_KG [NUMC (5)]
INCO1_KG_KG [CHAR (3)]
BUKRS_KG_KG [CHAR (4)]
MTART_KG_KG [CHAR (4)]
LLIEF_KG_KG [CHAR (10)]
LIFRE_KG_KG [CHAR (10)]
BSTME_KG_KG [UNIT (3)]
TAXIM_KG_KG [CHAR (1)]
TAXIK_KG_KG [CHAR (1)]
TAXIW_KG_KG [CHAR (1)]
TXJCD_KG_KG [CHAR (15)]
ERKRS_KG_KG [CHAR (4)]
VERSI_KG_KG [CHAR (3)]
VERSN_KG_KG [CHAR (3)]
VRGAR_KG_KG [CHAR (1)]
FKART_KG_KG [CHAR (4)]
VKORGAU_KG_KG [CHAR (4)]
HIENR_KG_KG [CHAR (10)]
VARCOND_KG_KG [CHAR (26)]
LAND1_KG_KG [CHAR (3)]
ZTERM_KG_KG [CHAR (4)]
GZOLX_KG_KG [CHAR (4)]
PWGGR_KG_KG [CHAR (6)]
VBELN_KG_KG [CHAR (10)]
POSNR_KG_KG [NUMC (6)]
UPMAT_KG_KG [CHAR (18)]
UKONM_KG_KG [CHAR (2)]
AUART_SD_KG_KG [CHAR (4)]
BUGRP_KG_KG [CHAR (6)]
VSTEL_KG_KG [CHAR (4)]
LPRIO_KG_KG [NUMC (2)]
LSTEL_KG_KG [CHAR (2)]
LADGR_KG_KG [CHAR (4)]
TRAGR_KG_KG [CHAR (4)]
MFRGR_KG_KG [CHAR (8)]
GARVZ_KG_KG [CHAR (6)]
GTART_KG_KG [CHAR (12)]
SHTYP_KG_KG [CHAR (4)]
TPLST_KG_KG [CHAR (4)]
VSBED_KG_KG [CHAR (2)]
ROUTE_KG_KG [CHAR (6)]
ADD01_KG_KG [CHAR (10)]
ADD02_KG_KG [CHAR (10)]
ADD03_KG_KG [CHAR (10)]
ADD04_KG_KG [CHAR (10)]
TDLNR_FA_KG_KG [CHAR (10)]
VHART_KG_KG [CHAR (4)]
VEGR1_KG_KG [CHAR (5)]
VEGR2_KG_KG [CHAR (5)]
VEGR3_KG_KG [CHAR (5)]
VEGR4_KG_KG [CHAR (5)]
VEGR5_KG_KG [CHAR (5)]
VHILM_KG_KG [CHAR (18)]
LANDT_KG_KG [CHAR (3)]
VSART_KG_KG [CHAR (2)]
TDLNR_KG_KG [CHAR (10)]
TDLNR_LND_KG_KG [CHAR (3)]
SDABW_KG_KG [CHAR (4)]
SLAND1_A_KG_KG [CHAR (3)]
SLAND1_Z_KG_KG [CHAR (3)]
KNOTA_KG_KG [CHAR (10)]
LAND1A_KG_KG [CHAR (3)]

WB2_KEY_CHANGE-MATKL_KG_KG = T023-MATKL
WB2_KEY_CHANGE-EKORG_KG_KG = T024E-EKORG
WB2_KEY_CHANGE-MTART_KG_KG = T134-MTART
WB2_KEY_CHANGE-BWTAR_KG_KG = T149D-BWTAR
WB2_KEY_CHANGE-KDGRP_KG_KG = T151-KDGRP
WB2_KEY_CHANGE-BZIRK_KG_KG = T171-BZIRK
WB2_KEY_CHANGE-VSART_KG_KG = T173-VSART
WB2_KEY_CHANGE-KONDM_KG_KG = T178-KONDM
WB2_KEY_CHANGE-UKONM_KG_KG = T178-KONDM
WB2_KEY_CHANGE-PRDHA_KG_KG = T179-PRODH
WB2_KEY_CHANGE-PRODH_KG_KG = T179-PRODH
WB2_KEY_CHANGE-KONDA_KG_KG = T188-KONDA
WB2_KEY_CHANGE-PLTYP_KG_KG = T189-PLTYP
WB2_KEY_CHANGE-COIMP_KG_KG = T604-STAWN
WB2_KEY_CHANGE-STAWN_KG_KG = T604-STAWN
WB2_KEY_CHANGE-GZOLX_KG_KG = T604G-GZOLX
WB2_KEY_CHANGE-PWGGR_KG_KG = T604WG-PWGGR
WB2_KEY_CHANGE-COADI_KG_KG = T610A-COADI
WB2_KEY_CHANGE-CASNR_KG_KG = T610C-CASNR
WB2_KEY_CHANGE-COPHA_KG_KG = T610D-COPHA
WB2_KEY_CHANGE-COKON_KG_KG = T610K-COKON
WB2_KEY_CHANGE-KTNUM_KG_KG = T610KP-KTPLN
WB2_KEY_CHANGE-PLNUM_KG_KG = T610KP-KTPLN
WB2_KEY_CHANGE-EILGR_KG_KG = T610LG-EILGR
WB2_KEY_CHANGE-PREFA_KG_KG = T610PA-PREFA
WB2_KEY_CHANGE-EXPRF_KG_KG = T616-EXPRF

0..N

T179
MANDT [CLNT (3)]
PRODH [CHAR (18)]

T188
MANDT [CLNT (3)]
KONDA [CHAR (2)]

T189
MANDT [CLNT (3)]
PLTYP [CHAR (2)]

T604
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
STAWN [CHAR (17)]

T604G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
GZOLX [CHAR (4)]

T604WG
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
PWGGR [CHAR (6)]

T610A
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COADI [CHAR (6)]

T610C
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
CASNR [CHAR (15)]

T610D
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COPHA [CHAR (6)]

T610K
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COKON [CHAR (6)]

T610KP
MANDT [CLNT (3)]
EILAN [CHAR (3)]
KTPLV [CHAR (2)]
KTPLN [CHAR (10)]

T610LG
MANDT [CLNT (3)]
EILAN [CHAR (3)]
EILGR [CHAR (10)]

T610PA
MANDT [CLNT (3)]
EILAN [CHAR (3)]
PREFA [CHAR (10)]

LZONEA_KG_KG [CHAR (10)]
REGIOA_KG_KG [CHAR (3)]
TRFZNA_KG_KG [CHAR (10)]
KNOTZ_KG_KG [CHAR (10)]
LAND1Z_KG_KG [CHAR (3)]
LZONEZ_KG_KG [CHAR (10)]
REGIOZ_KG_KG [CHAR (3)]
TRFZNZ_KG_KG [CHAR (10)]
SRVPOS_KG_KG [CHAR (18)]
RKE_MAABC_KG_KG [CHAR (1)]
BZIRK_KG_KG [CHAR (6)]
VKGRP_KG_KG [CHAR (3)]
BRSCH_KG_KG [CHAR (4)]
VKBUR_KG_KG [CHAR (4)]
PRCTR_KG_KG [CHAR (10)]
PPRCTR_KG_KG [CHAR (10)]
REP_MATNR_KG_KG [CHAR (18)]
LHIENR_KG_KG [CHAR (10)]
KDKGR_KG_KG [CHAR (2)]
J_1AFITP_KG_KG [CHAR (2)]
J_1ARFZ_KG_KG [CHAR (1)]
J_1AREGIO_KG_KG [CHAR (3)]
J_1AGICD_KG_KG [CHAR (2)]
J_1ADTYP_KG_KG [CHAR (2)]
J_1ATXREL_KG_KG [CHAR (10)]
VKAUS_KG_KG [CHAR (3)]
J_1AINDXP_KG_KG [CHAR (5)]
HLAND_KG_KG [CHAR (3)]
AUSFU_KG_KG [CHAR (10)]
HERKL_KG_KG [CHAR (3)]
VERLD_KG_KG [CHAR (3)]
COIMP_KG_KG [CHAR (17)]
STAWN_KG_KG [CHAR (17)]
CASNR_KG_KG [CHAR (15)]
EXPRF_KG_KG [CHAR (8)]
COKON_KG_KG [CHAR (6)]
COPHA_KG_KG [CHAR (6)]
COADI_KG_KG [CHAR (6)]
HERSE_KG_KG [CHAR (10)]
KTNUM_KG_KG [CHAR (10)]
PLNUM_KG_KG [CHAR (10)]
PREFA_KG_KG [CHAR (10)]
EILGR_KG_KG [CHAR (10)]
DELCO_KG_KG [CHAR (3)]
RESRC_KG_KG [CHAR (10)]
BEMOT_KG_KG [CHAR (2)]
KNUMA_AG_KG_KG [CHAR (10)]
KNUMA_PI_KG_KG [CHAR (10)]
KUNAG_KG_KG [CHAR (10)]
KUNWE_KG_KG [CHAR (10)]
KUNRG_KG_KG [CHAR (10)]
KUNRE_KG_KG [CHAR (10)]
MOGRU_KG_KG [CHAR (6)]
KBSTAT_KG_KG [CHAR (2)]
AUGRU_KG_KG [CHAR (3)]
BBYNR_KG_KG [CHAR (12)]
CNAE_KG_KG [CHAR (7)]
ICMSTAXPAY_KG_KG [CHAR (2)]
INDTYP_KG_KG [CHAR (2)]
TDT_KG_KG [CHAR (2)]
COMSIZE_KG_KG [CHAR (2)]
DECREGPC_KG_KG [CHAR (2)]
LEGALNAT_KG_KG [NUMC (4)]
EXTWG_KG_KG [CHAR (18)]
PRDHA_KG_KG [CHAR (18)]
MSR_RET_REASON_KG_KG [CHAR (3)]




MSR_REFUND_CODE_KG_KG [CHAR (3)]
HIER_ID_KG_KG [CHAR (2)]
NODE_KG_KG [CHAR (18)]
EXP_CLASS_KG [CHAR (3)]
ACC_TYPE_KG [CHAR (1)]
POST_TYPE_KG [CHAR (1)]
MANDT_KH [CLNT (3)]
KVEWE_KH [CHAR (1)]
KOTABNR_KH [NUMC (3)]
KAPPL_KH [CHAR (2)]
KSCHL_KH [CHAR (4)]
KZUST_KH [CHAR (3)]
KNUMA_PI_KH [CHAR (10)]
KNUMA_AG_KH [CHAR (10)]
KNUMA_SQ_KH [CHAR (10)]
KNUMA_SD_KH [CHAR (10)]
KNUMA_BO_KH [CHAR (10)]
WB2_KEY_CHANGE-KOKRS_KG_KG = TKA01-KOKRS
WB2_KEY_CHANGE-KOSAR_KG_KG = TKA05-KOSAR
WB2_KEY_CHANGE-ERKRS_KG_KG = TKEB-ERKRS
WB2_KEY_CHANGE-VERSI_KG_KG = TKVS-VERSI
WB2_KEY_CHANGE-VERSN_KG_KG = TKVS-VERSI
WB2_KEY_CHANGE-ZSCHL_KG_KG = TKZSL-ZSCHL
WB2_KEY_CHANGE-LADGR_KG_KG = TLGR-LADGR
WB2_KEY_CHANGE-MFRGR_KG_KG = TMFG-MFRGR
WB2_KEY_CHANGE-TAXIK_KG_KG = TMKK1-TAXIK
WB2_KEY_CHANGE-TAXIM_KG_KG = TMKM1-TAXIM
WB2_KEY_CHANGE-TAXIW_KG_KG = TMKW1-TAXIW
WB2_KEY_CHANGE-LPRIO_KG_KG = TPRIO-LPRIO
WB2_KEY_CHANGE-TAXK1_KG_KG = TSKD-TAXKD
WB2_KEY_CHANGE-TAXK2_KG_KG = TSKD-TAXKD
WB2_KEY_CHANGE-TAXK3_KG_KG = TSKD-TAXKD
WB2_KEY_CHANGE-TAXK4_KG_KG = TSKD-TAXKD
WB2_KEY_CHANGE-TAXK5_KG_KG = TSKD-TAXKD
WB2_KEY_CHANGE-TAXK6_KG_KG = TSKD-TAXKD
WB2_KEY_CHANGE-TAXK7_KG_KG = TSKD-TAXKD
WB2_KEY_CHANGE-TAXK8_KG_KG = TSKD-TAXKD
WB2_KEY_CHANGE-TAXK9_KG_KG = TSKD-TAXKD
WB2_KEY_CHANGE-TAXM1_KG_KG = TSKM-TAXKM
WB2_KEY_CHANGE-TAXM2_KG_KG = TSKM-TAXKM
WB2_KEY_CHANGE-TAXM3_KG_KG = TSKM-TAXKM
WB2_KEY_CHANGE-TAXM4_KG_KG = TSKM-TAXKM
WB2_KEY_CHANGE-TAXM5_KG_KG = TSKM-TAXKM
WB2_KEY_CHANGE-TAXM6_KG_KG = TSKM-TAXKM
WB2_KEY_CHANGE-TAXM7_KG_KG = TSKM-TAXKM
WB2_KEY_CHANGE-TAXM8_KG_KG = TSKM-TAXKM
WB2_KEY_CHANGE-TAXM9_KG_KG = TSKM-TAXKM
WB2_KEY_CHANGE-SPART_KG_KG = TSPA-SPART
WB2_KEY_CHANGE-TPLST_KG_KG = TTDS-TPLST
WB2_KEY_CHANGE-TRAGR_KG_KG = TTGR-TRAGR
TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
TKA05
MANDT [CLNT (3)]
KOSAR [CHAR (1)]
TKEB
MANDT [CLNT (3)]
ERKRS [CHAR (4)]
TKVS
MANDT [CLNT (3)]
VERSI [CHAR (3)]
TKZSL
MANDT [CLNT (3)]
ZSCHL [CHAR (6)]
TLGR
MANDT [CLNT (3)]
LADGR [CHAR (4)]
TMFG
MANDT [CLNT (3)]
MFRGR [CHAR (8)]
TMKK1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIK [CHAR (1)]
TMKM1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIM [CHAR (1)]
TMKW1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIW [CHAR (1)]
TPRIO
MANDT [CLNT (3)]
LPRIO [NUMC (2)]
TSKD
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKD [CHAR (1)]
TSKM
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKM [CHAR (1)]
TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]
TTDS
MANDT [CLNT (3)]
TPLST [CHAR (4)]
TTGR
MANDT [CLNT (3)]
TRAGR [CHAR (4)]


WB2_KEY_CHANGE-TXJCD_KG_KG = TTXJ-TXJCD
TTXJ
MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (15)]
0..N
WB2_KEY_CHANGE-AUART_SD_KG_KG = TVAK-AUART
TVAK
MANDT [CLNT (3)]
AUART [CHAR (4)]
0..N
WB2_KEY_CHANGE-VARCOND_KG_KG = TVARC-VARCOND
TVARC
MANDT [CLNT (3)]
VARCOND [CHAR (26)]
0..N
WB2_KEY_CHANGE-AUGRU_KG_KG = TVAU-AUGRU
TVAU
MANDT [CLNT (3)]
AUGRU [CHAR (3)]
0..N
WB2_KEY_CHANGE-BONUS_KG_KG = TVBO-BONUS
TVBO
MANDT [CLNT (3)]
BONUS [CHAR (2)]
0..N
WB2_KEY_CHANGE-VKBUR_KG_KG = TVBUR-VKBUR
TVBUR
MANDT [CLNT (3)]
VKBUR [CHAR (4)]
0..N
WB2_KEY_CHANGE-DELCO_KG_KG = TVDC-DELCO
TVDC
MANDT [CLNT (3)]
DELCO [CHAR (3)]
0..N
WB2_KEY_CHANGE-VEGR1_KG_KG = TVE1-VEGR1
TVE1
MANDT [CLNT (3)]
VEGR1 [CHAR (5)]
0..N
WB2_KEY_CHANGE-VEGR2_KG_KG = TVE2-VEGR2
TVE2
MANDT [CLNT (3)]
VEGR2 [CHAR (5)]
0..N
WB2_KEY_CHANGE-VEGR3_KG_KG = TVE3-VEGR3
TVE3
MANDT [CLNT (3)]
VEGR3 [CHAR (5)]
0..N
WB2_KEY_CHANGE-VEGR4_KG_KG = TVE4-VEGR4
TVE4
MANDT [CLNT (3)]
VEGR4 [CHAR (5)]
0..N
WB2_KEY_CHANGE-VEGR5_KG_KG = TVE5-VEGR5
TVE5
MANDT [CLNT (3)]
VEGR5 [CHAR (5)]
0..N
WB2_KEY_CHANGE-BUGRP_KG_KG = TVFBWG-BUGRP
TVFBWG
MANDT [CLNT (3)]
KAPPL [CHAR (2)]
BUGRP [CHAR (6)]
0..N
WB2_KEY_CHANGE-FKART_KG_KG = TVFK-FKART
TVFK
MANDT [CLNT (3)]
FKART [CHAR (4)]
0..N
WB2_KEY_CHANGE-TRFZNA_KG_KG = TVFTZ-TRFZN
TVFTZ
MANDT [CLNT (3)]
TRFZN [CHAR (10)]
0..N
WB2_KEY_CHANGE-TRFZNZ_KG_KG = TVFTZ-TRFZN
0..N
WB2_KEY_CHANGE-VRGAR_KG_KG = TVGA-VRGAR
TVGA
MANDT [CLNT (3)]
VRGAR [CHAR (1)]
0..N
WB2_KEY_CHANGE-KDKGR_KG_KG = TVKGG-KDKGR
TVKGG
MANDT [CLNT (3)]
KDKGR [CHAR (2)]
0..N
WB2_KEY_CHANGE-VKGRP_KG_KG = TVKGR-VKGRP
TVKGR
MANDT [CLNT (3)]
VKGRP [CHAR (3)]
0..N
WB2_KEY_CHANGE-KNOTA_KG_KG = TVKN-KNOTE


WB2_KEY_CHANGE-KNOTZ_KG_KG = TVKN-KNOTE
0..N
0..N
TVKN
MANDT [CLNT (3)]
KNOTE [CHAR (10)]
WB2_KEY_CHANGE-VKORGAU_KG_KG = TVKO-VKORG
WB2_KEY_CHANGE-VKORG_KG_KG = TVKO-VKORG
0..N
0..N
TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]
WB2_KEY_CHANGE-LSTEL_KG_KG = TVLA-LSTEL
TVLA
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
LSTEL [CHAR (2)]
0..N
WB2_KEY_CHANGE-VKAUS_KG_KG = TVLV-ABRVW
TVLV
MANDT [CLNT (3)]
ABRVW [CHAR (3)]
0..N
WB2_KEY_CHANGE-PROVG_KG_KG = TVPR-PROVG
TVPR
MANDT [CLNT (3)]
PROVG [CHAR (2)]
0..N
WB2_KEY_CHANGE-ROUTE_KG_KG = TVRO-ROUTE
TVRO
MANDT [CLNT (3)]
ROUTE [CHAR (6)]
0..N
WB2_KEY_CHANGE-SDABW_KG_KG = TVSAK-SDABW
TVSAK
MANDT [CLNT (3)]
SDABW [CHAR (4)]
0..N
WB2_KEY_CHANGE-VSBED_KG_KG = TVSB-VSBED
TVSB
MANDT [CLNT (3)]
VSBED [CHAR (2)]
0..N
WB2_KEY_CHANGE-VSTEL_KG_KG = TVST-VSTEL
TVST
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
0..N
WB2_KEY_CHANGE-SHTYP_KG_KG = TVTK-SHTYP
TVTK
MANDT [CLNT (3)]
SHTYP [CHAR (4)]
0..N
WB2_KEY_CHANGE-VTWEG_KG_KG = TVTW-VTWEG
TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]
0..N
WB2_KEY_CHANGE-VHART_KG_KG = TVTY-TRATY
TVTY
MANDT [CLNT (3)]
TRATY [CHAR (4)]
0..N
WB2_KEY_CHANGE-ZTERM_KG_KG = TVZB-ZTERM
TVZB
MANDT [CLNT (3)]
ZTERM [CHAR (4)]
0..N
WB2_KEY_CHANGE-ACC_TYPE_KG = TWBACCTYPE-ACC_TYPE
TWBACCTYPE
MANDT [CLNT (3)]
ACC_TYPE [CHAR (1)]
0..N
WB2_KEY_CHANGE-EXP_CLASS_KG = TWBEXCLASS-EXP_CLASS
TWBEXCLASS
MANDT [CLNT (3)]
EXP_CLASS [CHAR (3)]
0..N


WB2_KEY_CHANGE-POST_TYPE_KG = TWBPOSTTYPE-POST_TYPE
TWBPOSTTYPE
MANDT [CLNT (3)]
POST_TYPE [CHAR (1)]
0..N
WB2_KEY_CHANGE-EXTWG_KG_KG = TWEW-EXTWG
TWEW
MANDT [CLNT (3)]
EXTWG [CHAR (18)]
0..N
WB2_KEY_CHANGE-LZONEA_KG_KG = TZONE-ZONE1
WB2_KEY_CHANGE-LZONEZ_KG_KG = TZONE-ZONE1
TZONE
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
ZONE1 [CHAR (10)]
0..N
0..N
WB2_KEY_CHANGE-VBELN_KG_KG = VBUK-VBELN
VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]
0..N
WB2_KEY_CHANGE-POSNR_KG_KG = VBUP-POSNR
VBUP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
0..N
WB2_KEY_CHANGE-ADD01_KG_KG = VTADD01-ADD_INFO
VTADD01
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
WB2_KEY_CHANGE-ADD02_KG_KG = VTADD02-ADD_INFO
VTADD02
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
WB2_KEY_CHANGE-ADD03_KG_KG = VTADD03-ADD_INFO
VTADD03
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
WB2_KEY_CHANGE-ADD04_KG_KG = VTADD04-ADD_INFO
VTADD04
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
WB2_KEY_CHANGE-HIER_ID_KG_KG = WRF_MATGRP_HIER-HIER_ID
WRF_MATGRP_HIER
MANDT [CLNT (3)]
HIER_ID [CHAR (2)]
0..N
WB2_KEY_CHANGE-NODE_KG_KG = WRF_MATGRP_STRUC-NODE
WRF_MATGRP_STRUC
MANDT [CLNT (3)]
HIER_ID [CHAR (2)]
NODE [CHAR (18)]
DATE_FROM [DATS (8)]
0..N
WB2_KEY_CHANGE-LTSNR_KG_KG = WYT1-LTSNR
WYT1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
LTSNR [CHAR (6)]
0..N