SAP ABAP table WB2_KOMG {Allowed Fields for Condition Structures}




WB2_KOMG-J_1ATXREL_KG = J_1ATXREL-J_1ATXREL
0..N
J_1ATXREL
MANDT [CLNT (3)]
J_1ATXREL [CHAR (10)]
WB2_KOMG-CNAE_KG = J_1BTCNAE-J_1BCNAE
0..N
J_1BTCNAE
MANDT [CLNT (3)]
J_1BCNAE [CHAR (7)]
WB2_KOMG-COMSIZE_KG = J_1BTCOMSIZE-J_1BCOMSIZE
0..N
J_1BTCOMSIZE
MANDT [CLNT (3)]
J_1BCOMSIZE [CHAR (2)]
WB2_KOMG-DECREGPC_KG = J_1BTDECREGPC-J_1BDECREGPC
0..N
J_1BTDECREGPC
MANDT [CLNT (3)]
J_1BDECREGPC [CHAR (2)]
WB2_KOMG-ICMSTAXPAY_KG = J_1BTICMSTAXPAY-J_1BICMSTAXPAY
0..N
J_1BTICMSTAXPAY
MANDT [CLNT (3)]
J_1BICMSTAXPAY [CHAR (2)]
WB2_KOMG-INDTYP_KG = J_1BTINDTYP-J_1BINDTYP
0..N
J_1BTINDTYP
MANDT [CLNT (3)]
J_1BINDTYP [CHAR (2)]
WB2_KOMG-LEGALNAT_KG = J_1BTLEGALNAT-J_1BLEGALNAT
0..N
J_1BTLEGALNAT
MANDT [CLNT (3)]
J_1BLEGALNAT [NUMC (4)]
WB2_KOMG-TDT_KG = J_1BTTDT-J_1BTDT
0..N
J_1BTTDT
MANDT [CLNT (3)]
J_1BTTDT [CHAR (2)]
WB2_KOMG-HIENR_KG = KNA1-KUNNR
WB2_KOMG-KUNAG_KG = KNA1-KUNNR
WB2_KOMG-KUNNR_KG = KNA1-KUNNR
WB2_KOMG-KUNRE_KG = KNA1-KUNNR
WB2_KOMG-KUNRG_KG = KNA1-KUNNR
WB2_KOMG-KUNWE_KG = KNA1-KUNNR
0..N
KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]
WB2_KOMG-KNUMA_AG_KG = KONA-KNUMA
WB2_KOMG-KNUMA_PI_KG = KONA-KNUMA
0..N
KONA
MANDT [CLNT (3)]
KNUMA [CHAR (10)]
WB2_KOMG-BBYNR_KG = KONBBYH-BBYNR
0..N
KONBBYH
MANDT [CLNT (3)]
BBYNR [CHAR (12)]
WB2_KOMG-AUSFU_KG = LFA1-LIFNR
WB2_KOMG-HERSE_KG = LFA1-LIFNR
WB2_KOMG-KOLIF_KG = LFA1-LIFNR
WB2_KOMG-LHIENR_KG = LFA1-LIFNR
WB2_KOMG-LIFNR_KG = LFA1-LIFNR
WB2_KOMG-LIFRE_KG = LFA1-LIFNR
WB2_KOMG-LLIEF_KG = LFA1-LIFNR
WB2_KOMG-TDLNR_FA_KG = LFA1-LIFNR
WB2_KOMG-TDLNR_KG = LFA1-LIFNR
0..N
LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
WB2_KOMG-MATNR_KG = MARA-MATNR
0..N
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
0..N
MCHA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
CHARG [CHAR (10)]
0..N
MSR_C_RET_REASON
MANDT [CLNT (3)]
RET_REASON [CHAR (3)]
0..N


WB2_KOMG
MANDT_KG [CLNT (3)]
VKORG_KG [CHAR (4)]
VTWEG_KG [CHAR (2)]
SPART_KG [CHAR (2)]
KUNNR_KG [CHAR (10)]
KDGRP_KG [CHAR (2)]
PLTYP_KG [CHAR (2)]
KONDA_KG [CHAR (2)]
KONDM_KG [CHAR (2)]
WAERK_KG [CUKY (5)]
MATNR_KG [CHAR (18)]
BWTAR_KG [CHAR (10)]
CHARG_KG [CHAR (10)]
PRODH_KG [CHAR (18)]
MEINS_KG [UNIT (3)]
BONUS_KG [CHAR (2)]
PROVG_KG [CHAR (2)]
ALAND_KG [CHAR (3)]
WKREG_KG [CHAR (3)]
LLAND_KG [CHAR (3)]
REGIO_KG [CHAR (3)]
COUNC_KG [CHAR (3)]
CITYC_KG [CHAR (4)]
TAXM1_KG [CHAR (1)]
TAXM2_KG [CHAR (1)]
TAXM3_KG [CHAR (1)]
TAXM4_KG [CHAR (1)]
TAXM5_KG [CHAR (1)]
TAXM6_KG [CHAR (1)]
TAXM7_KG [CHAR (1)]
WB2_KOMG-UPMAT_KG = MARA-MATNR
WB2_KOMG-VHILM_KG = MARA-MATNR
WB2_KOMG-CHARG_KG = MCHA-CHARG
WB2_KOMG-MSR_RET_REASON_KG = MSR_C_RET_REASON-RET_REASON
WB2_KOMG-MSR_REFUND_CODE_KG = MSR_C_RET_REFUND-RETURNS_REFUND
WB2_KOMG-MANDT_KG = T000-MANDT
WB2_KOMG-BUKRS_KG = T001-BUKRS
WB2_KOMG-RESWK_KG = T001W-WERKS
WB2_KOMG-WERKS_KG = T001W-WERKS
WB2_KOMG-WERKV_KG = T001W-WERKS
WB2_KOMG-AUART_KG = T003O-AUART
WB2_KOMG-ALAND_KG = T005-LAND1
WB2_KOMG-HERKL_KG = T005-LAND1
WB2_KOMG-HLAND_KG = T005-LAND1
WB2_KOMG-LAND1A_KG = T005-LAND1
WB2_KOMG-LAND1Z_KG = T005-LAND1
WB2_KOMG-LAND1_KG = T005-LAND1
WB2_KOMG-LANDT_KG = T005-LAND1
WB2_KOMG-LLAND_KG = T005-LAND1
WB2_KOMG-SLAND1_A_KG = T005-LAND1
WB2_KOMG-SLAND1_Z_KG = T005-LAND1
WB2_KOMG-TDLNR_LND_KG = T005-LAND1
WB2_KOMG-VERLD_KG = T005-LAND1
WB2_KOMG-COUNC_KG = T005E-COUNC
WB2_KOMG-CITYC_KG = T005G-CITYC
WB2_KOMG-J_1AREGIO_KG = T005S-BLAND
WB2_KOMG-REGIOA_KG = T005S-BLAND
WB2_KOMG-REGIOZ_KG = T005S-BLAND
WB2_KOMG-REGIO_KG = T005S-BLAND
WB2_KOMG-WKREG_KG = T005S-BLAND
WB2_KOMG-BSTME_KG = T006-MSEHI
MSR_C_RET_REFUND
MANDT [CLNT (3)]
RETURNS_REFUND [CHAR (3)]
T000
MANDT [CLNT (3)]
T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
T003O
CLIENT [CLNT (3)]
AUART [CHAR (4)]
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
T005E
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
COUNC [CHAR (3)]
T005G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
CITYC [CHAR (4)]
T005S
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
T016
MANDT [CLNT (3)]
BRSCH [CHAR (4)]
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]
T134
MANDT [CLNT (3)]
MTART [CHAR (4)]
T149D
0..N
1

TAXM8_KG [CHAR (1)]
TAXM9_KG [CHAR (1)]
TAXK1_KG [CHAR (1)]
TAXK2_KG [CHAR (1)]
TAXK3_KG [CHAR (1)]
TAXK4_KG [CHAR (1)]
TAXK5_KG [CHAR (1)]
TAXK6_KG [CHAR (1)]
TAXK7_KG [CHAR (1)]
TAXK8_KG [CHAR (1)]
TAXK9_KG [CHAR (1)]
LIFNR_KG [CHAR (10)]
MATKL_KG [CHAR (9)]
EKORG_KG [CHAR (4)]
WERKS_KG [CHAR (4)]
RESWK_KG [CHAR (4)]
KOLIF_KG [CHAR (10)]
LTSNR_KG [CHAR (6)]
WERKV_KG [CHAR (4)]
VRKME_KG [UNIT (3)]
GSBER_KG [CHAR (4)]
AUART_KG [CHAR (4)]
ZSCHL_KG [CHAR (6)]
KOSTV_KG [CHAR (10)]
MEEIN_KG [UNIT (3)]
KOKRS_KG [CHAR (4)]
KOSAR_KG [CHAR (1)]
INFNR_KG [CHAR (10)]
EVRTN_KG [CHAR (10)]
EVRTP_KG [NUMC (5)]
INCO1_KG [CHAR (3)]
BUKRS_KG [CHAR (4)]
MTART_KG [CHAR (4)]
LLIEF_KG [CHAR (10)]
LIFRE_KG [CHAR (10)]
BSTME_KG [UNIT (3)]
TAXIM_KG [CHAR (1)]
TAXIK_KG [CHAR (1)]
TAXIW_KG [CHAR (1)]
TXJCD_KG [CHAR (15)]
ERKRS_KG [CHAR (4)]
VERSI_KG [CHAR (3)]
VERSN_KG [CHAR (3)]
VRGAR_KG [CHAR (1)]
FKART_KG [CHAR (4)]
VKORGAU_KG [CHAR (4)]
HIENR_KG [CHAR (10)]
VARCOND_KG [CHAR (26)]
LAND1_KG [CHAR (3)]
ZTERM_KG [CHAR (4)]
GZOLX_KG [CHAR (4)]
PWGGR_KG [CHAR (6)]
VBELN_KG [CHAR (10)]
POSNR_KG [NUMC (6)]
UPMAT_KG [CHAR (18)]
UKONM_KG [CHAR (2)]
AUART_SD_KG [CHAR (4)]
BUGRP_KG [CHAR (6)]
VSTEL_KG [CHAR (4)]
LPRIO_KG [NUMC (2)]
LSTEL_KG [CHAR (2)]
LADGR_KG [CHAR (4)]
TRAGR_KG [CHAR (4)]
MFRGR_KG [CHAR (8)]
GARVZ_KG [CHAR (6)]
GTART_KG [CHAR (12)]
SHTYP_KG [CHAR (4)]
TPLST_KG [CHAR (4)]

WB2_KOMG-MEEIN_KG = T006-MSEHI
WB2_KOMG-MEINS_KG = T006-MSEHI
WB2_KOMG-VRKME_KG = T006-MSEHI
WB2_KOMG-BRSCH_KG = T016-BRSCH
WB2_KOMG-MATKL_KG = T023-MATKL
WB2_KOMG-EKORG_KG = T024E-EKORG
WB2_KOMG-MTART_KG = T134-MTART
WB2_KOMG-BWTAR_KG = T149D-BWTAR
WB2_KOMG-KDGRP_KG = T151-KDGRP
WB2_KOMG-BZIRK_KG = T171-BZIRK
WB2_KOMG-VSART_KG = T173-VSART
WB2_KOMG-KONDM_KG = T178-KONDM
WB2_KOMG-UKONM_KG = T178-KONDM
WB2_KOMG-PRDHA_KG = T179-PRODH
WB2_KOMG-PRODH_KG = T179-PRODH
WB2_KOMG-KONDA_KG = T188-KONDA
WB2_KOMG-PLTYP_KG = T189-PLTYP
WB2_KOMG-COIMP_KG = T604-STAWN
WB2_KOMG-STAWN_KG = T604-STAWN
WB2_KOMG-GZOLX_KG = T604G-GZOLX
WB2_KOMG-PWGGR_KG = T604WG-PWGGR
WB2_KOMG-COADI_KG = T610A-COADI
WB2_KOMG-CASNR_KG = T610C-CASNR
WB2_KOMG-COPHA_KG = T610D-COPHA
WB2_KOMG-COKON_KG = T610K-COKON
WB2_KOMG-KTNUM_KG = T610KP-KTPLN

0..N

T151
MANDT [CLNT (3)]
KDGRP [CHAR (2)]

T171
MANDT [CLNT (3)]
BZIRK [CHAR (6)]

T173
MANDT [CLNT (3)]
VSART [CHAR (2)]

T178
MANDT [CLNT (3)]
KONDM [CHAR (2)]

T179
MANDT [CLNT (3)]
PRODH [CHAR (18)]

T188
MANDT [CLNT (3)]
KONDA [CHAR (2)]

T189
MANDT [CLNT (3)]
PLTYP [CHAR (2)]

T604
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
STAWN [CHAR (17)]

T604G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
GZOLX [CHAR (4)]

T604WG
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
PWGGR [CHAR (6)]

T610A
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COADI [CHAR (6)]

T610C
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
CASNR [CHAR (15)]

T610D
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COPHA [CHAR (6)]

T610K
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COKON [CHAR (6)]

T610KP
MANDT [CLNT (3)]
BWTAR [CHAR (10)]

VSBED_KG [CHAR (2)]
ROUTE_KG [CHAR (6)]
ADD01_KG [CHAR (10)]
ADD02_KG [CHAR (10)]
ADD03_KG [CHAR (10)]
ADD04_KG [CHAR (10)]
TDLNR_FA_KG [CHAR (10)]
VHART_KG [CHAR (4)]
VEGR1_KG [CHAR (5)]
VEGR2_KG [CHAR (5)]
VEGR3_KG [CHAR (5)]
VEGR4_KG [CHAR (5)]
VEGR5_KG [CHAR (5)]
VHILM_KG [CHAR (18)]
LANDT_KG [CHAR (3)]
VSART_KG [CHAR (2)]
TDLNR_KG [CHAR (10)]
TDLNR_LND_KG [CHAR (3)]
SDABW_KG [CHAR (4)]
SLAND1_A_KG [CHAR (3)]
SLAND1_Z_KG [CHAR (3)]
KNOTA_KG [CHAR (10)]
LAND1A_KG [CHAR (3)]
LZONEA_KG [CHAR (10)]
REGIOA_KG [CHAR (3)]
TRFZNA_KG [CHAR (10)]
KNOTZ_KG [CHAR (10)]
LAND1Z_KG [CHAR (3)]
LZONEZ_KG [CHAR (10)]
REGIOZ_KG [CHAR (3)]
TRFZNZ_KG [CHAR (10)]
SRVPOS_KG [CHAR (18)]
RKE_MAABC_KG [CHAR (1)]
BZIRK_KG [CHAR (6)]
VKGRP_KG [CHAR (3)]
BRSCH_KG [CHAR (4)]
VKBUR_KG [CHAR (4)]
PRCTR_KG [CHAR (10)]
PPRCTR_KG [CHAR (10)]
REP_MATNR_KG [CHAR (18)]
LHIENR_KG [CHAR (10)]
KDKGR_KG [CHAR (2)]
J_1AFITP_KG [CHAR (2)]
J_1ARFZ_KG [CHAR (1)]
J_1AREGIO_KG [CHAR (3)]
J_1AGICD_KG [CHAR (2)]
J_1ADTYP_KG [CHAR (2)]
J_1ATXREL_KG [CHAR (10)]
VKAUS_KG [CHAR (3)]
J_1AINDXP_KG [CHAR (5)]
HLAND_KG [CHAR (3)]
AUSFU_KG [CHAR (10)]
HERKL_KG [CHAR (3)]
VERLD_KG [CHAR (3)]
COIMP_KG [CHAR (17)]
STAWN_KG [CHAR (17)]
CASNR_KG [CHAR (15)]
EXPRF_KG [CHAR (8)]
COKON_KG [CHAR (6)]
COPHA_KG [CHAR (6)]
COADI_KG [CHAR (6)]
HERSE_KG [CHAR (10)]

0..N WB2_KOMG-PLNUM_KG = T610KP-KTPLN 0..N

T610KP
MANDT [CLNT (3)]
EILAN [CHAR (3)]
KTPLV [CHAR (2)]
KTPLN [CHAR (10)]

0..N WB2_KOMG-EILGR_KG = T610LG-EILGR 0..N

T610LG
MANDT [CLNT (3)]
EILAN [CHAR (3)]
EILGR [CHAR (10)]

0..N WB2_KOMG-PREFA_KG = T610PA-PREFA 0..N

T610PA
MANDT [CLNT (3)]
EILAN [CHAR (3)]
PREFA [CHAR (10)]

0..N WB2_KOMG-EXPRF_KG = T616-EXPRF 0..N

T616
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
EXPRF [CHAR (8)]

0..N WB2_KOMG-MOGRU_KG = T618G-MOGRU 0..N

T618G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
MOGRU [CHAR (6)]

1 WB2_KOMG-KBSTAT_KG = T686E-KBSTAT 1

T686E
MANDT [CLNT (3)]
KBSTAT [CHAR (2)]

0..N WB2_KOMG-REP_MATNR_KG = T8A60-REP_MATNR 0..N

T8A60
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
REP_MATNR [CHAR (18)]

0..N WB2_KOMG-BEMOT_KG = TBMOT-BEMOT 0..N

TBMOT
MANDT [CLNT (3)]
BEMOT [CHAR (2)]

0..N WB2_KOMG-WAERK_KG = TCURC-WAERS 0..N

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

0..N WB2_KOMG-GTART_KG = TGAR-GTART 0..N

TGAR
MANDT [CLNT (3)]
GARVZ [CHAR (6)]
GTART [CHAR (12)]

0..N WB2_KOMG-GARVZ_KG = TGAV-GARVZ 0..N

TGAV
MANDT [CLNT (3)]
GARVZ [CHAR (6)]

0..N WB2_KOMG-GSBER_KG = TGSB-GSBER 0..N

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

0..N WB2_KOMG-INCO1_KG = TINC-INCO1 0..N

TINC
MANDT [CLNT (3)]
INCO1 [CHAR (3)]


KTNUM_KG [CHAR (10)]
PLNUM_KG [CHAR (10)]
PREFA_KG [CHAR (10)]
EILGR_KG [CHAR (10)]
DELCO_KG [CHAR (3)]
RESRC_KG [CHAR (10)]
BEMOT_KG [CHAR (2)]
KNUMA_AG_KG [CHAR (10)]
KNUMA_PI_KG [CHAR (10)]
KUNAG_KG [CHAR (10)]
KUNWE_KG [CHAR (10)]
KUNRG_KG [CHAR (10)]
KUNRE_KG [CHAR (10)]
MOGRU_KG [CHAR (6)]
KBSTAT_KG [CHAR (2)]
AUGRU_KG [CHAR (3)]
BBYNR_KG [CHAR (12)]
CNAE_KG [CHAR (7)]
ICMSTAXPAY_KG [CHAR (2)]
INDTYP_KG [CHAR (2)]
TDT_KG [CHAR (2)]
COMSIZE_KG [CHAR (2)]
DECREGPC_KG [CHAR (2)]
LEGALNAT_KG [NUMC (4)]
EXTWG_KG [CHAR (18)]
PRDHA_KG [CHAR (18)]
MSR_RET_REASON_KG [CHAR (3)]
MSR_REFUND_CODE_KG [CHAR (3)]
HIER_ID_KG [CHAR (2)]
NODE_KG [CHAR (18)]
EXP_CLASS [CHAR (3)]
ACC_TYPE [CHAR (1)]
POST_TYPE [CHAR (1)]
WB2_KOMG-KOKRS_KG = TKA01-KOKRS
WB2_KOMG-KOSAR_KG = TKA05-KOSAR
WB2_KOMG-ERKRS_KG = TKEB-ERKRS
WB2_KOMG-VERSI_KG = TKVS-VERSI
WB2_KOMG-VERSN_KG = TKVS-VERSI
WB2_KOMG-ZSCHL_KG = TKZSL-ZSCHL
WB2_KOMG-LADGR_KG = TLGR-LADGR
WB2_KOMG-MFRGR_KG = TMFG-MFRGR
WB2_KOMG-TAXIK_KG = TMKK1-TAXIK
WB2_KOMG-TAXIM_KG = TMKM1-TAXIM
WB2_KOMG-TAXIW_KG = TMKW1-TAXIW
WB2_KOMG-LPRIO_KG = TPRIO-LPRIO
WB2_KOMG-TAXK1_KG = TSKD-TAXKD
WB2_KOMG-TAXK2_KG = TSKD-TAXKD
WB2_KOMG-TAXK3_KG = TSKD-TAXKD
WB2_KOMG-TAXK4_KG = TSKD-TAXKD
WB2_KOMG-TAXK5_KG = TSKD-TAXKD
WB2_KOMG-TAXK6_KG = TSKD-TAXKD
WB2_KOMG-TAXK7_KG = TSKD-TAXKD
WB2_KOMG-TAXK8_KG = TSKD-TAXKD
WB2_KOMG-TAXK9_KG = TSKD-TAXKD
WB2_KOMG-TAXM1_KG = TSKM-TAXKM
WB2_KOMG-TAXM2_KG = TSKM-TAXKM
WB2_KOMG-TAXM3_KG = TSKM-TAXKM
WB2_KOMG-TAXM4_KG = TSKM-TAXKM
WB2_KOMG-TAXM5_KG = TSKM-TAXKM
WB2_KOMG-TAXM6_KG = TSKM-TAXKM
WB2_KOMG-TAXM7_KG = TSKM-TAXKM
WB2_KOMG-TAXM8_KG = TSKM-TAXKM
WB2_KOMG-TAXM9_KG = TSKM-TAXKM
WB2_KOMG-SPART_KG = TSPA-SPART
TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
TKA05
MANDT [CLNT (3)]
KOSAR [CHAR (1)]
TKEB
MANDT [CLNT (3)]
ERKRS [CHAR (4)]
TKVS
MANDT [CLNT (3)]
VERSI [CHAR (3)]
TKZSL
MANDT [CLNT (3)]
ZSCHL [CHAR (6)]
TLGR
MANDT [CLNT (3)]
LADGR [CHAR (4)]
TMFG
MANDT [CLNT (3)]
MFRGR [CHAR (8)]
TMKK1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIK [CHAR (1)]
TMKM1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIM [CHAR (1)]
TMKW1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIW [CHAR (1)]
TPRIO
MANDT [CLNT (3)]
LPRIO [NUMC (2)]
TSKD
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKD [CHAR (1)]
TSKM
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKM [CHAR (1)]
TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]
0..N
1


WB2_KOMG-TPLST_KG = TTDS-TPLST
0..N
TTDS
MANDT [CLNT (3)]
TPLST [CHAR (4)]
WB2_KOMG-TRAGR_KG = TTGR-TRAGR
0..N
TTGR
MANDT [CLNT (3)]
TRAGR [CHAR (4)]
WB2_KOMG-TXJCD_KG = TTXJ-TXJCD
0..N
TTXJ
MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (15)]
WB2_KOMG-AUART_SD_KG = TVAK-AUART
0..N
TVAK
MANDT [CLNT (3)]
AUART [CHAR (4)]
WB2_KOMG-VARCOND_KG = TVARC-VARCOND
0..N
TVARC
MANDT [CLNT (3)]
VARCOND [CHAR (26)]
WB2_KOMG-AUGRU_KG = TVAU-AUGRU
0..N
TVAU
MANDT [CLNT (3)]
AUGRU [CHAR (3)]
WB2_KOMG-BONUS_KG = TVBO-BONUS
0..N
TVBO
MANDT [CLNT (3)]
BONUS [CHAR (2)]
WB2_KOMG-VKBUR_KG = TVBUR-VKBUR
0..N
TVBUR
MANDT [CLNT (3)]
VKBUR [CHAR (4)]
WB2_KOMG-DELCO_KG = TVDC-DELCO
0..N
TVDC
MANDT [CLNT (3)]
DELCO [CHAR (3)]
WB2_KOMG-VEGR1_KG = TVE1-VEGR1
0..N
TVE1
MANDT [CLNT (3)]
VEGR1 [CHAR (5)]
WB2_KOMG-VEGR2_KG = TVE2-VEGR2
0..N
TVE2
MANDT [CLNT (3)]
VEGR2 [CHAR (5)]
WB2_KOMG-VEGR3_KG = TVE3-VEGR3
0..N
TVE3
MANDT [CLNT (3)]
VEGR3 [CHAR (5)]
WB2_KOMG-VEGR4_KG = TVE4-VEGR4
0..N
TVE4
MANDT [CLNT (3)]
VEGR4 [CHAR (5)]
WB2_KOMG-VEGR5_KG = TVE5-VEGR5
0..N
TVE5
MANDT [CLNT (3)]
VEGR5 [CHAR (5)]
WB2_KOMG-BUGRP_KG = TVFBWG-BUGRP
0..N
TVFBWG
MANDT [CLNT (3)]
KAPPL [CHAR (2)]
BUGRP [CHAR (6)]
WB2_KOMG-FKART_KG = TVFK-FKART
0..N
TVFK
MANDT [CLNT (3)]
FKART [CHAR (4)]
WB2_KOMG-TRFZNA_KG = TVFTZ-TRFZN


WB2_KOMG-TRFZNZ_KG = TVFTZ-TRFZN
0..N
0..N
TVFTZ
MANDT [CLNT (3)]
TRFZN [CHAR (10)]
WB2_KOMG-VRGAR_KG = TVGA-VRGAR
0..N
TVGA
MANDT [CLNT (3)]
VRGAR [CHAR (1)]
WB2_KOMG-KDKGR_KG = TVKGG-KDKGR
0..N
TVKGG
MANDT [CLNT (3)]
KDKGR [CHAR (2)]
WB2_KOMG-VKGRP_KG = TVKGR-VKGRP
0..N
TVKGR
MANDT [CLNT (3)]
VKGRP [CHAR (3)]
WB2_KOMG-KNOTA_KG = TVKN-KNOTE
WB2_KOMG-KNOTZ_KG = TVKN-KNOTE
0..N
0..N
TVKN
MANDT [CLNT (3)]
KNOTE [CHAR (10)]
WB2_KOMG-VKORGAU_KG = TVKO-VKORG
WB2_KOMG-VKORG_KG = TVKO-VKORG
0..N
0..N
TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]
WB2_KOMG-LSTEL_KG = TVLA-LSTEL
0..N
TVLA
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
LSTEL [CHAR (2)]
WB2_KOMG-VKAUS_KG = TVLV-ABRVW
0..N
TVLV
MANDT [CLNT (3)]
ABRVW [CHAR (3)]
WB2_KOMG-PROVG_KG = TVPR-PROVG
0..N
TVPR
MANDT [CLNT (3)]
PROVG [CHAR (2)]
WB2_KOMG-ROUTE_KG = TVRO-ROUTE
0..N
TVRO
MANDT [CLNT (3)]
ROUTE [CHAR (6)]
WB2_KOMG-SDABW_KG = TVSAK-SDABW
0..N
TVSAK
MANDT [CLNT (3)]
SDABW [CHAR (4)]
WB2_KOMG-VSBED_KG = TVSB-VSBED
0..N
TVSB
MANDT [CLNT (3)]
VSBED [CHAR (2)]
WB2_KOMG-VSTEL_KG = TVST-VSTEL
0..N
TVST
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
WB2_KOMG-SHTYP_KG = TVTK-SHTYP
0..N
TVTK
MANDT [CLNT (3)]
SHTYP [CHAR (4)]


WB2_KOMG-VTWEG_KG = TVTW-VTWEG
0..N
TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]
WB2_KOMG-VHART_KG = TVTY-TRATY
0..N
TVTY
MANDT [CLNT (3)]
TRATY [CHAR (4)]
WB2_KOMG-ZTERM_KG = TVZB-ZTERM
0..N
TVZB
MANDT [CLNT (3)]
ZTERM [CHAR (4)]
WB2_KOMG-ACC_TYPE = TWBACCTYPE-ACC_TYPE
0..N
TWBACCTYPE
MANDT [CLNT (3)]
ACC_TYPE [CHAR (1)]
WB2_KOMG-EXP_CLASS = TWBEXCLASS-EXP_CLASS
0..N
TWBEXCLASS
MANDT [CLNT (3)]
EXP_CLASS [CHAR (3)]
WB2_KOMG-POST_TYPE = TWBPOSTTYPE-POST_TYPE
0..N
TWBPOSTTYPE
MANDT [CLNT (3)]
POST_TYPE [CHAR (1)]
WB2_KOMG-EXTWG_KG = TWEW-EXTWG
0..N
TWEW
MANDT [CLNT (3)]
EXTWG [CHAR (18)]
WB2_KOMG-LZONEA_KG = TZONE-ZONE1
0..N
TZONE
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
ZONE1 [CHAR (10)]
WB2_KOMG-LZONEZ_KG = TZONE-ZONE1
0..N
WB2_KOMG-VBELN_KG = VBUK-VBELN
0..N
VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]
WB2_KOMG-POSNR_KG = VBUP-POSNR
0..N
VBUP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
WB2_KOMG-ADD01_KG = VTADD01-ADD_INFO
0..N
VTADD01
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
WB2_KOMG-ADD02_KG = VTADD02-ADD_INFO
0..N
VTADD02
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
WB2_KOMG-ADD03_KG = VTADD03-ADD_INFO
0..N
VTADD03
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
WB2_KOMG-ADD04_KG = VTADD04-ADD_INFO
0..N
VTADD04
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
WB2_KOMG-HIER_ID_KG = WRF_MATGRP_HIER-HIER_ID
0..N
WRF_MATGRP_HIER
MANDT [CLNT (3)]
HIER_ID [CHAR (2)]
WB2_KOMG-NODE_KG = WRF_MATGRP_STRUC-NODE
0..N
WRF_MATGRP_STRUC
MANDT [CLNT (3)]
HIER_ID [CHAR (2)]
NODE [CHAR (18)]
DATE_FROM [DATS (8)]
WB2_KOMG-LTSNR_KG = WYT1-LTSNR
0..N
WYT1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
LTSNR [CHAR (6)]