SAP ABAP table WCB_COND_DISP {Condition Display Structure for ALV}




WCB_COND_DISP-J_1ATXREL_KG_KG = J_1ATXREL-J_1ATXREL
J_1ATXREL
MANDT [CLNT (3)]
J_1ATXREL [CHAR (10)]
WCB_COND_DISP-CNAE_KG_KG = J_1BTCNAE-J_1BCNAE
J_1BTCNAE
MANDT [CLNT (3)]
J_1BCNAE [CHAR (7)]
WCB_COND_DISP-COMSIZE_KG_KG = J_1BTCOMSIZE-J_1BCOMSIZE
J_1BTCOMSIZE
MANDT [CLNT (3)]
J_1BCOMSIZE [CHAR (2)]
WCB_COND_DISP-DECREGPC_KG_KG = J_1BTDECREGPC-J_1BDECREGPC
J_1BTDECREGPC
MANDT [CLNT (3)]
J_1BDECREGPC [CHAR (2)]
WCB_COND_DISP-ICMSTAXPAY_KG_KG = J_1BTICMSTAXPAY-J_1BICMSTAXPAY
J_1BTICMSTAXPAY
MANDT [CLNT (3)]
J_1BICMSTAXPAY [CHAR (2)]
WCB_COND_DISP-INDTYP_KG_KG = J_1BTINDTYP-J_1BINDTYP
J_1BTINDTYP
MANDT [CLNT (3)]
J_1BINDTYP [CHAR (2)]
WCB_COND_DISP-LEGALNAT_KG_KG = J_1BTLEGALNAT-J_1BLEGALNAT
J_1BTLEGALNAT
MANDT [CLNT (3)]
J_1BLEGALNAT [NUMC (4)]
WCB_COND_DISP-TDT_KG_KG = J_1BTTDT-J_1BTDT
J_1BTTDT
MANDT [CLNT (3)]
J_1BTDT [CHAR (2)]
WCB_COND_DISP-HIENR_KG_KG = KNA1-KUNNR
WCB_COND_DISP-KUNAG_KG_KG = KNA1-KUNNR
WCB_COND_DISP-KUNNR_KG_KG = KNA1-KUNNR
WCB_COND_DISP-KUNNR_KP = KNA1-KUNNR
WCB_COND_DISP-KUNRE_KG_KG = KNA1-KUNNR
WCB_COND_DISP-KUNRG_KG_KG = KNA1-KUNNR
WCB_COND_DISP-KUNWE_KG_KG = KNA1-KUNNR
KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]
WCB_COND_DISP-KNUMA_AG_KG_KG = KONA-KNUMA
WCB_COND_DISP-KNUMA_AG_KH = KONA-KNUMA
WCB_COND_DISP-KNUMA_AG_KP = KONA-KNUMA
WCB_COND_DISP-KNUMA_BO_KH = KONA-KNUMA
WCB_COND_DISP-KNUMA_BO_KP = KONA-KNUMA
WCB_COND_DISP-KNUMA_PI_KG_KG = KONA-KNUMA
WCB_COND_DISP-KNUMA_PI_KH = KONA-KNUMA
WCB_COND_DISP-KNUMA_PI_KP = KONA-KNUMA
WCB_COND_DISP-KNUMA_SD_KH = KONA-KNUMA
WCB_COND_DISP-KNUMA_SQ_KH = KONA-KNUMA
WCB_COND_DISP-KNUMA_SQ_KP = KONA-KNUMA
KONA
MANDT [CLNT (3)]
KNUMA [CHAR (10)]
WCB_COND_DISP-BBYNR_KG_KG = KONBBYH-BBYNR
KONBBYH
MANDT [CLNT (3)]
BBYNR [CHAR (12)]
WCB_COND_DISP-AUSFU_KG_KG = LFA1-LIFNR
WCB_COND_DISP-HERSE_KG_KG = LFA1-LIFNR
WCB_COND_DISP-KOLIF_KG_KG = LFA1-LIFNR
WCB_COND_DISP-LHIENR_KG_KG = LFA1-LIFNR
LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
MCHA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
CHARG [CHAR (10)]
0..N


WCB_COND_DISP
MANDT_KG_KG [CLNT (3)]
VKORG_KG_KG [CHAR (4)]
VTWEG_KG_KG [CHAR (2)]
SPART_KG_KG [CHAR (2)]
KUNNR_KG_KG [CHAR (10)]
KDGRP_KG_KG [CHAR (2)]
PLTYP_KG_KG [CHAR (2)]
KONDA_KG_KG [CHAR (2)]
KONDM_KG_KG [CHAR (2)]
WAERK_KG_KG [CUKY (5)]
MATNR_KG_KG [CHAR (18)]
BWTAR_KG_KG [CHAR (10)]
CHARG_KG_KG [CHAR (10)]
PRODH_KG_KG [CHAR (18)]
MEINS_KG_KG [UNIT (3)]
BONUS_KG_KG [CHAR (2)]
PROVG_KG_KG [CHAR (2)]
ALAND_KG_KG [CHAR (3)]
WKREG_KG_KG [CHAR (3)]
LLAND_KG_KG [CHAR (3)]
REGIO_KG_KG [CHAR (3)]
COUNC_KG_KG [CHAR (3)]
CITYC_KG_KG [CHAR (4)]
TAXM1_KG_KG [CHAR (1)]
TAXM2_KG_KG [CHAR (1)]
TAXM3_KG_KG [CHAR (1)]
TAXM4_KG_KG [CHAR (1)]
TAXM5_KG_KG [CHAR (1)]
TAXM6_KG_KG [CHAR (1)]
TAXM7_KG_KG [CHAR (1)]
TAXM8_KG_KG [CHAR (1)]
TAXM9_KG_KG [CHAR (1)]
TAXK1_KG_KG [CHAR (1)]
TAXK2_KG_KG [CHAR (1)]
TAXK3_KG_KG [CHAR (1)]
TAXK4_KG_KG [CHAR (1)]
TAXK5_KG_KG [CHAR (1)]
TAXK6_KG_KG [CHAR (1)]
TAXK7_KG_KG [CHAR (1)]
WCB_COND_DISP-LIFNR_KG_KG = LFA1-LIFNR
WCB_COND_DISP-LIFNR_KP = LFA1-LIFNR
WCB_COND_DISP-LIFRE_KG_KG = LFA1-LIFNR
WCB_COND_DISP-LLIEF_KG_KG = LFA1-LIFNR
WCB_COND_DISP-TDLNR_FA_KG_KG = LFA1-LIFNR
WCB_COND_DISP-TDLNR_KG_KG = LFA1-LIFNR
WCB_COND_DISP-BOMAT_KP = MARA-MATNR
WCB_COND_DISP-MATNR_KG_KG = MARA-MATNR
WCB_COND_DISP-UPMAT_KG_KG = MARA-MATNR
WCB_COND_DISP-VHILM_KG_KG = MARA-MATNR
WCB_COND_DISP-CHARG_KG_KG = MCHA-CHARG
WCB_COND_DISP-MSR_RET_REASON_KG_KG = MSR_C_RET_REASON-RET_REASON
WCB_COND_DISP-MSR_REFUND_CODE_KG_KG = MSR_C_RET_REFUND-RETURNS_REFUND
WCB_COND_DISP-MANDT_KG_KG = T000-MANDT
WCB_COND_DISP-MANDT_KH = T000-MANDT
WCB_COND_DISP-MANDT_KP = T000-MANDT
WCB_COND_DISP-BUKRS_KG_KG = T001-BUKRS
WCB_COND_DISP-RESWK_KG_KG = T001W-WERKS
WCB_COND_DISP-WERKS_KG_KG = T001W-WERKS
WCB_COND_DISP-WERKV_KG_KG = T001W-WERKS
WCB_COND_DISP-AUART_KG_KG = T003O-AUART
WCB_COND_DISP-ALAND_KG_KG = T005-LAND1
WCB_COND_DISP-HERKL_KG_KG = T005-LAND1
WCB_COND_DISP-HLAND_KG_KG = T005-LAND1
WCB_COND_DISP-LAND1A_KG_KG = T005-LAND1
WCB_COND_DISP-LAND1Z_KG_KG = T005-LAND1
WCB_COND_DISP-LAND1_KG_KG = T005-LAND1
WCB_COND_DISP-LANDT_KG_KG = T005-LAND1
WCB_COND_DISP-LLAND_KG_KG = T005-LAND1
WCB_COND_DISP-SLAND1_A_KG_KG = T005-LAND1
WCB_COND_DISP-SLAND1_Z_KG_KG = T005-LAND1
MSR_C_RET_REASON
MANDT [CLNT (3)]
RET_REASON [CHAR (3)]
MSR_C_RET_REFUND
MANDT [CLNT (3)]
RETURNS_REFUND [CHAR (3)]
T000
MANDT [CLNT (3)]
T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
T003O
CLIENT [CLNT (3)]
AUART [CHAR (4)]
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
T005E
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
COUNC [CHAR (3)]
T005G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
REGIO [CHAR (3)]
CITYC [CHAR (4)]
T005S
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
T016
MANDT [CLNT (3)]
BRSCH [CHAR (4)]
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]

TAXK8_KG_KG [CHAR (1)]
TAXK9_KG_KG [CHAR (1)]
LIFNR_KG_KG [CHAR (10)]
MATKL_KG_KG [CHAR (9)]
EKORG_KG_KG [CHAR (4)]
WERKS_KG_KG [CHAR (4)]
RESWK_KG_KG [CHAR (4)]
KOLIF_KG_KG [CHAR (10)]
LTSNR_KG_KG [CHAR (6)]
WERKV_KG_KG [CHAR (4)]
VRKME_KG_KG [UNIT (3)]
GSBER_KG_KG [CHAR (4)]
AUART_KG_KG [CHAR (4)]
ZSCHL_KG_KG [CHAR (6)]
KOSTV_KG_KG [CHAR (10)]
MEEIN_KG_KG [UNIT (3)]
KOKRS_KG_KG [CHAR (4)]
KOSAR_KG_KG [CHAR (1)]
INFNR_KG_KG [CHAR (10)]
EVRTN_KG_KG [CHAR (10)]
EVRTP_KG_KG [NUMC (5)]
INCO1_KG_KG [CHAR (3)]
BUKRS_KG_KG [CHAR (4)]
MTART_KG_KG [CHAR (4)]
LLIEF_KG_KG [CHAR (10)]
LIFRE_KG_KG [CHAR (10)]
BSTME_KG_KG [UNIT (3)]
TAXIM_KG_KG [CHAR (1)]
TAXIK_KG_KG [CHAR (1)]
TAXIW_KG_KG [CHAR (1)]
TXJCD_KG_KG [CHAR (15)]
ERKRS_KG_KG [CHAR (4)]
VERSI_KG_KG [CHAR (3)]
VERSN_KG_KG [CHAR (3)]
VRGAR_KG_KG [CHAR (1)]
FKART_KG_KG [CHAR (4)]
VKORGAU_KG_KG [CHAR (4)]
HIENR_KG_KG [CHAR (10)]
VARCOND_KG_KG [CHAR (26)]
LAND1_KG_KG [CHAR (3)]
ZTERM_KG_KG [CHAR (4)]
GZOLX_KG_KG [CHAR (4)]
PWGGR_KG_KG [CHAR (6)]
VBELN_KG_KG [CHAR (10)]
POSNR_KG_KG [NUMC (6)]
UPMAT_KG_KG [CHAR (18)]
UKONM_KG_KG [CHAR (2)]
AUART_SD_KG_KG [CHAR (4)]
BUGRP_KG_KG [CHAR (6)]
VSTEL_KG_KG [CHAR (4)]
LPRIO_KG_KG [NUMC (2)]
LSTEL_KG_KG [CHAR (2)]
LADGR_KG_KG [CHAR (4)]
TRAGR_KG_KG [CHAR (4)]
MFRGR_KG_KG [CHAR (8)]
GARVZ_KG_KG [CHAR (6)]
GTART_KG_KG [CHAR (12)]
SHTYP_KG_KG [CHAR (4)]
TPLST_KG_KG [CHAR (4)]
VSBED_KG_KG [CHAR (2)]
ROUTE_KG_KG [CHAR (6)]
ADD01_KG_KG [CHAR (10)]
ADD02_KG_KG [CHAR (10)]
ADD03_KG_KG [CHAR (10)]
ADD04_KG_KG [CHAR (10)]
TDLNR_FA_KG_KG [CHAR (10)]
VHART_KG_KG [CHAR (4)]
VEGR1_KG_KG [CHAR (5)]
VEGR2_KG_KG [CHAR (5)]
VEGR3_KG_KG [CHAR (5)]
VEGR4_KG_KG [CHAR (5)]
VEGR5_KG_KG [CHAR (5)]
VHILM_KG_KG [CHAR (18)]

0..N WCB_COND_DISP-TDLNR_LND_KG_KG = T005-LAND1
0..N WCB_COND_DISP-VERLD_KG_KG = T005-LAND1
0..N WCB_COND_DISP-COUNC_KG_KG = T005E-COUNC
WCB_COND_DISP-CITYC_KG_KG = T005G-CITYC
WCB_COND_DISP-J_1AREGIO_KG_KG = T005S-BLAND
0..N
0..N WCB_COND_DISP-REGIOA_KG_KG = T005S-BLAND
1 WCB_COND_DISP-REGIOZ_KG_KG = T005S-BLAND
0..N
0..N WCB_COND_DISP-REGIO_KG_KG = T005S-BLAND
0..N WCB_COND_DISP-WKREG_KG_KG = T005S-BLAND
0..N WCB_COND_DISP-BSTME_KG_KG = T006-MSEHI
WCB_COND_DISP-KMEIN_KP = T006-MSEHI
0..N
0..N WCB_COND_DISP-KONMS_KP = T006-MSEHI
{0,1} WCB_COND_DISP-MEEIN_KG_KG = T006-MSEHI
{0,1} WCB_COND_DISP-MEINS_KG_KG = T006-MSEHI
0..N
WCB_COND_DISP-MEINS_KP = T006-MSEHI
0..N
WCB_COND_DISP-VRKME_KG_KG = T006-MSEHI
{0,1} WCB_COND_DISP-BRSCH_KG_KG = T016-BRSCH
0..N WCB_COND_DISP-MATKL_KG_KG = T023-MATKL
0..N WCB_COND_DISP-EKORG_KG_KG = T024E-EKORG
0..N WCB_COND_DISP-MTART_KG_KG = T134-MTART
0..N WCB_COND_DISP-BWTAR_KG_KG = T149D-BWTAR
0..N WCB_COND_DISP-KDGRP_KG_KG = T151-KDGRP
0..N WCB_COND_DISP-BZIRK_KG_KG = T171-BZIRK
0..N WCB_COND_DISP-VSART_KG_KG = T173-VSART
0..N WCB_COND_DISP-KONDM_KG_KG = T178-KONDM
0..N WCB_COND_DISP-UKONM_KG_KG = T178-KONDM
0..N WCB_COND_DISP-PRDHA_KG_KG = T179-PRODH
0..N WCB_COND_DISP-PRODH_KG_KG = T179-PRODH
0..N WCB_COND_DISP-KONDA_KG_KG = T188-KONDA
0..N WCB_COND_DISP-PLTYP_KG_KG = T189-PLTYP
0..N WCB_COND_DISP-COIMP_KG_KG = T604-STAWN
0..N
0..N WCB_COND_DISP-STAWN_KG_KG = T604-STAWN
0..N WCB_COND_DISP-GZOLX_KG_KG = T604G-GZOLX
0..N WCB_COND_DISP-PWGGR_KG_KG = T604WG-PWGGR
0..N WCB_COND_DISP-COADI_KG_KG = T610A-COADI
0..N
0..N WCB_COND_DISP-CASNR_KG_KG = T610C-CASNR

T134
MANDT [CLNT (3)]
MTART [CHAR (4)]

T149D
MANDT [CLNT (3)]
BWTAR [CHAR (10)]

T151
MANDT [CLNT (3)]
KDGRP [CHAR (2)]

T171
MANDT [CLNT (3)]
BZIRK [CHAR (6)]

T173
MANDT [CLNT (3)]
VSART [CHAR (2)]

T178
MANDT [CLNT (3)]
KONDM [CHAR (2)]

T179
MANDT [CLNT (3)]
PRODH [CHAR (18)]

T188
MANDT [CLNT (3)]
KONDA [CHAR (2)]

T189
MANDT [CLNT (3)]
PLTYP [CHAR (2)]

T604
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
STAWN [CHAR (17)]

T604G
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
GZOLX [CHAR (4)]

T604WG
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
PWGGR [CHAR (6)]

T610A
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COADI [CHAR (6)]

T610C
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
CASNR [CHAR (15)]

T610D
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COPHA [CHAR (6)]

T610K
MANDT [CLNT (3)]
EILAN [CHAR (3)]
COKON [CHAR (6)]

LANDT_KG_KG [CHAR (3)]
VSART_KG_KG [CHAR (2)]
TDLNR_KG_KG [CHAR (10)]
TDLNR_LND_KG_KG [CHAR (3)]
SDABW_KG_KG [CHAR (4)]
SLAND1_A_KG_KG [CHAR (3)]
SLAND1_Z_KG_KG [CHAR (3)]
KNOTA_KG_KG [CHAR (10)]
LAND1A_KG_KG [CHAR (3)]
LZONEA_KG_KG [CHAR (10)]
REGIOA_KG_KG [CHAR (3)]
TRFZNA_KG_KG [CHAR (10)]
KNOTZ_KG_KG [CHAR (10)]
LAND1Z_KG_KG [CHAR (3)]
LZONEZ_KG_KG [CHAR (10)]
REGIOZ_KG_KG [CHAR (3)]
TRFZNZ_KG_KG [CHAR (10)]
SRVPOS_KG_KG [CHAR (18)]
RKE_MAABC_KG_KG [CHAR (1)]
BZIRK_KG_KG [CHAR (6)]
VKGRP_KG_KG [CHAR (3)]
BRSCH_KG_KG [CHAR (4)]
VKBUR_KG_KG [CHAR (4)]
PRCTR_KG_KG [CHAR (10)]
PPRCTR_KG_KG [CHAR (10)]
REP_MATNR_KG_KG [CHAR (18)]
LHIENR_KG_KG [CHAR (10)]
KDKGR_KG_KG [CHAR (2)]
J_1AFITP_KG_KG [CHAR (2)]
J_1ARFZ_KG_KG [CHAR (1)]
J_1AREGIO_KG_KG [CHAR (3)]
J_1AGICD_KG_KG [CHAR (2)]
J_1ADTYP_KG_KG [CHAR (2)]
J_1ATXREL_KG_KG [CHAR (10)]
VKAUS_KG_KG [CHAR (3)]
J_1AINDXP_KG_KG [CHAR (5)]
HLAND_KG_KG [CHAR (3)]
AUSFU_KG_KG [CHAR (10)]
HERKL_KG_KG [CHAR (3)]
VERLD_KG_KG [CHAR (3)]
COIMP_KG_KG [CHAR (17)]
STAWN_KG_KG [CHAR (17)]
CASNR_KG_KG [CHAR (15)]
EXPRF_KG_KG [CHAR (8)]
COKON_KG_KG [CHAR (6)]
COPHA_KG_KG [CHAR (6)]
COADI_KG_KG [CHAR (6)]
HERSE_KG_KG [CHAR (10)]
KTNUM_KG_KG [CHAR (10)]
PLNUM_KG_KG [CHAR (10)]
PREFA_KG_KG [CHAR (10)]
EILGR_KG_KG [CHAR (10)]
DELCO_KG_KG [CHAR (3)]
RESRC_KG_KG [CHAR (10)]
BEMOT_KG_KG [CHAR (2)]
KNUMA_AG_KG_KG [CHAR (10)]
KNUMA_PI_KG_KG [CHAR (10)]
KUNAG_KG_KG [CHAR (10)]
KUNWE_KG_KG [CHAR (10)]
KUNRG_KG_KG [CHAR (10)]
KUNRE_KG_KG [CHAR (10)]
MOGRU_KG_KG [CHAR (6)]
KBSTAT_KG_KG [CHAR (2)]
AUGRU_KG_KG [CHAR (3)]
BBYNR_KG_KG [CHAR (12)]
CNAE_KG_KG [CHAR (7)]
ICMSTAXPAY_KG_KG [CHAR (2)]
INDTYP_KG_KG [CHAR (2)]
TDT_KG_KG [CHAR (2)]
COMSIZE_KG_KG [CHAR (2)]
DECREGPC_KG_KG [CHAR (2)]
LEGALNAT_KG_KG [NUMC (4)]
EXTWG_KG_KG [CHAR (18)]
PRDHA_KG_KG [CHAR (18)]
MSR_RET_REASON_KG_KG [CHAR (3)]
MSR_REFUND_CODE_KG_KG [CHAR (3)]




HIER_ID_KG_KG [CHAR (2)]
NODE_KG_KG [CHAR (18)]
MANDT_KP [CLNT (3)]
KAPPL_KP [CHAR (2)]
KSCHL_KP [CHAR (4)]
KONMS_KP [UNIT (3)]
KONWS_KP [CUKY (5)]
KONWA_KP [CUKY (5)]
KMEIN_KP [UNIT (3)]
MEINS_KP [UNIT (3)]
KWAEH_KP [CUKY (5)]
KZNEP_KP [CHAR (1)]
KUNNR_KP [CHAR (10)]
LIFNR_KP [CHAR (10)]
BOMAT_KP [CHAR (18)]
KNUMA_PI_KP [CHAR (10)]
KNUMA_AG_KP [CHAR (10)]
KNUMA_SQ_KP [CHAR (10)]
KNUMA_BO_KP [CHAR (10)]
VBEWA_KP [CHAR (4)]
MANDT_KH [CLNT (3)]
KVEWE_KH [CHAR (1)]
KOTABNR_KH [NUMC (3)]
KAPPL_KH [CHAR (2)]
KSCHL_KH [CHAR (4)]
KZUST_KH [CHAR (3)]
KNUMA_PI_KH [CHAR (10)]
KNUMA_AG_KH [CHAR (10)]
KNUMA_SQ_KH [CHAR (10)]
KNUMA_SD_KH [CHAR (10)]
KNUMA_BO_KH [CHAR (10)]
WCB_COND_DISP-GARVZ_KG_KG = TGAV-GARVZ
WCB_COND_DISP-GSBER_KG_KG = TGSB-GSBER
WCB_COND_DISP-INCO1_KG_KG = TINC-INCO1
WCB_COND_DISP-KOKRS_KG_KG = TKA01-KOKRS
WCB_COND_DISP-KOSAR_KG_KG = TKA05-KOSAR
WCB_COND_DISP-ERKRS_KG_KG = TKEB-ERKRS
WCB_COND_DISP-VERSI_KG_KG = TKVS-VERSI
WCB_COND_DISP-VERSN_KG_KG = TKVS-VERSI
WCB_COND_DISP-ZSCHL_KG_KG = TKZSL-ZSCHL
WCB_COND_DISP-LADGR_KG_KG = TLGR-LADGR
WCB_COND_DISP-MFRGR_KG_KG = TMFG-MFRGR
WCB_COND_DISP-TAXIK_KG_KG = TMKK1-TAXIK
WCB_COND_DISP-TAXIM_KG_KG = TMKM1-TAXIM
WCB_COND_DISP-TAXIW_KG_KG = TMKW1-TAXIW
WCB_COND_DISP-LPRIO_KG_KG = TPRIO-LPRIO
WCB_COND_DISP-TAXK1_KG_KG = TSKD-TAXKD
WCB_COND_DISP-TAXK2_KG_KG = TSKD-TAXKD
WCB_COND_DISP-TAXK3_KG_KG = TSKD-TAXKD
WCB_COND_DISP-TAXK4_KG_KG = TSKD-TAXKD
WCB_COND_DISP-TAXK5_KG_KG = TSKD-TAXKD
WCB_COND_DISP-TAXK6_KG_KG = TSKD-TAXKD
WCB_COND_DISP-TAXK7_KG_KG = TSKD-TAXKD
WCB_COND_DISP-TAXK8_KG_KG = TSKD-TAXKD
WCB_COND_DISP-TAXK9_KG_KG = TSKD-TAXKD
WCB_COND_DISP-TAXM1_KG_KG = TSKM-TAXKM
WCB_COND_DISP-TAXM2_KG_KG = TSKM-TAXKM
WCB_COND_DISP-TAXM3_KG_KG = TSKM-TAXKM
WCB_COND_DISP-TAXM4_KG_KG = TSKM-TAXKM
WCB_COND_DISP-TAXM5_KG_KG = TSKM-TAXKM
WCB_COND_DISP-TAXM6_KG_KG = TSKM-TAXKM
WCB_COND_DISP-TAXM7_KG_KG = TSKM-TAXKM
WCB_COND_DISP-TAXM8_KG_KG = TSKM-TAXKM
WCB_COND_DISP-TAXM9_KG_KG = TSKM-TAXKM
WCB_COND_DISP-SPART_KG_KG = TSPA-SPART
TGAV
MANDT [CLNT (3)]
GARVZ [CHAR (6)]
TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]
TINC
MANDT [CLNT (3)]
INCO1 [CHAR (3)]
TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
TKA05
MANDT [CLNT (3)]
KOSAR [CHAR (1)]
TKEB
MANDT [CLNT (3)]
ERKRS [CHAR (4)]
TKVS
MANDT [CLNT (3)]
VERSI [CHAR (3)]
TKZSL
MANDT [CLNT (3)]
ZSCHL [CHAR (6)]
TLGR
MANDT [CLNT (3)]
LADGR [CHAR (4)]
TMFG
MANDT [CLNT (3)]
MFRGR [CHAR (8)]
TMKK1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIK [CHAR (1)]
TMKM1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIM [CHAR (1)]
TMKW1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIW [CHAR (1)]
TPRIO
MANDT [CLNT (3)]
LPRIO [NUMC (2)]
TSKD
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKD [CHAR (1)]
TSKM
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKM [CHAR (1)]
TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]
0..N
1


WCB_COND_DISP-TPLST_KG_KG = TTDS-TPLST
TTDS
MANDT [CLNT (3)]
TPLST [CHAR (4)]
0..N
WCB_COND_DISP-TRAGR_KG_KG = TTGR-TRAGR
TTGR
MANDT [CLNT (3)]
TRAGR [CHAR (4)]
0..N
WCB_COND_DISP-TXJCD_KG_KG = TTXJ-TXJCD
TTXJ
MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (15)]
0..N
WCB_COND_DISP-AUART_SD_KG_KG = TVAK-AUART
TVAK
MANDT [CLNT (3)]
AUART [CHAR (4)]
0..N
WCB_COND_DISP-VARCOND_KG_KG = TVARC-VARCOND
TVARC
MANDT [CLNT (3)]
VARCOND [CHAR (26)]
0..N
WCB_COND_DISP-AUGRU_KG_KG = TVAU-AUGRU
TVAU
MANDT [CLNT (3)]
AUGRU [CHAR (3)]
0..N
WCB_COND_DISP-BONUS_KG_KG = TVBO-BONUS
TVBO
MANDT [CLNT (3)]
BONUS [CHAR (2)]
0..N
WCB_COND_DISP-VKBUR_KG_KG = TVBUR-VKBUR
TVBUR
MANDT [CLNT (3)]
VKBUR [CHAR (4)]
0..N
WCB_COND_DISP-DELCO_KG_KG = TVDC-DELCO
TVDC
MANDT [CLNT (3)]
DELCO [CHAR (3)]
0..N
WCB_COND_DISP-VEGR1_KG_KG = TVE1-VEGR1
TVE1
MANDT [CLNT (3)]
VEGR1 [CHAR (5)]
0..N
WCB_COND_DISP-VEGR2_KG_KG = TVE2-VEGR2
TVE2
MANDT [CLNT (3)]
VEGR2 [CHAR (5)]
0..N
WCB_COND_DISP-VEGR3_KG_KG = TVE3-VEGR3
TVE3
MANDT [CLNT (3)]
VEGR3 [CHAR (5)]
0..N
WCB_COND_DISP-VEGR4_KG_KG = TVE4-VEGR4
TVE4
MANDT [CLNT (3)]
VEGR4 [CHAR (5)]
0..N
WCB_COND_DISP-VEGR5_KG_KG = TVE5-VEGR5
TVE5
MANDT [CLNT (3)]
VEGR5 [CHAR (5)]
0..N
WCB_COND_DISP-BUGRP_KG_KG = TVFBWG-BUGRP
TVFBWG
MANDT [CLNT (3)]
KAPPL [CHAR (2)]
BUGRP [CHAR (6)]
0..N
WCB_COND_DISP-FKART_KG_KG = TVFK-FKART
TVFK
MANDT [CLNT (3)]
FKART [CHAR (4)]
0..N
WCB_COND_DISP-TRFZNA_KG_KG = TVFTZ-TRFZN


WCB_COND_DISP-TRFZNZ_KG_KG = TVFTZ-TRFZN
0..N
0..N
TVFTZ
MANDT [CLNT (3)]
TRFZN [CHAR (10)]
WCB_COND_DISP-VRGAR_KG_KG = TVGA-VRGAR
0..N
TVGA
MANDT [CLNT (3)]
VRGAR [CHAR (1)]
WCB_COND_DISP-KDKGR_KG_KG = TVKGG-KDKGR
0..N
TVKGG
MANDT [CLNT (3)]
KDKGR [CHAR (2)]
WCB_COND_DISP-VKGRP_KG_KG = TVKGR-VKGRP
0..N
TVKGR
MANDT [CLNT (3)]
VKGRP [CHAR (3)]
WCB_COND_DISP-KNOTA_KG_KG = TVKN-KNOTE
WCB_COND_DISP-KNOTZ_KG_KG = TVKN-KNOTE
0..N
0..N
TVKN
MANDT [CLNT (3)]
KNOTE [CHAR (10)]
WCB_COND_DISP-VKORGAU_KG_KG = TVKO-VKORG
WCB_COND_DISP-VKORG_KG_KG = TVKO-VKORG
0..N
0..N
TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]
WCB_COND_DISP-LSTEL_KG_KG = TVLA-LSTEL
0..N
TVLA
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
LSTEL [CHAR (2)]
WCB_COND_DISP-VKAUS_KG_KG = TVLV-ABRVW
0..N
TVLV
MANDT [CLNT (3)]
ABRVW [CHAR (3)]
WCB_COND_DISP-PROVG_KG_KG = TVPR-PROVG
0..N
TVPR
MANDT [CLNT (3)]
PROVG [CHAR (2)]
WCB_COND_DISP-ROUTE_KG_KG = TVRO-ROUTE
0..N
TVRO
MANDT [CLNT (3)]
ROUTE [CHAR (6)]
WCB_COND_DISP-SDABW_KG_KG = TVSAK-SDABW
0..N
TVSAK
MANDT [CLNT (3)]
SDABW [CHAR (4)]
WCB_COND_DISP-VSBED_KG_KG = TVSB-VSBED
0..N
TVSB
MANDT [CLNT (3)]
VSBED [CHAR (2)]
WCB_COND_DISP-VSTEL_KG_KG = TVST-VSTEL
0..N
TVST
MANDT [CLNT (3)]
VSTEL [CHAR (4)]
WCB_COND_DISP-SHTYP_KG_KG = TVTK-SHTYP
0..N
TVTK
MANDT [CLNT (3)]
SHTYP [CHAR (4)]
WCB_COND_DISP-VTWEG_KG_KG = TVTW-VTWEG
0..N
TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]
WCB_COND_DISP-VHART_KG_KG = TVTY-TRATY
0..N
TVTY
MANDT [CLNT (3)]
TRATY [CHAR (4)]
WCB_COND_DISP-ZTERM_KG_KG = TVZB-ZTERM
0..N
TVZB
MANDT [CLNT (3)]
ZTERM [CHAR (4)]
WCB_COND_DISP-EXTWG_KG_KG = TWEW-EXTWG


TWEW
MANDT [CLNT (3)]
EXTWG [CHAR (18)]
WCB_COND_DISP-VBEWA_KP = TZB0A-SBEWART
0..N
TZB0A
MANDT [CLNT (3)]
RANTYP [CHAR (1)]
SBEWART [CHAR (4)]
WCB_COND_DISP-LZONEA_KG_KG = TZONE-ZONE1
0..N
TZONE
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
ZONE1 [CHAR (10)]
WCB_COND_DISP-LZONEZ_KG_KG = TZONE-ZONE1
0..N
0..N
WCB_COND_DISP-VBELN_KG_KG = VBUK-VBELN
VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]
0..N
WCB_COND_DISP-POSNR_KG_KG = VBUP-POSNR
VBUP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
0..N
WCB_COND_DISP-ADD01_KG_KG = VTADD01-ADD_INFO
VTADD01
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
WCB_COND_DISP-ADD02_KG_KG = VTADD02-ADD_INFO
VTADD02
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
WCB_COND_DISP-ADD03_KG_KG = VTADD03-ADD_INFO
VTADD03
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
WCB_COND_DISP-ADD04_KG_KG = VTADD04-ADD_INFO
VTADD04
MANDT [CLNT (3)]
ADD_INFO [CHAR (10)]
0..N
WCB_COND_DISP-HIER_ID_KG_KG = WRF_MATGRP_HIER-HIER_ID
WRF_MATGRP_HIER
MANDT [CLNT (3)]
HIER_ID [CHAR (2)]
0..N
WCB_COND_DISP-NODE_KG_KG = WRF_MATGRP_STRUC-NODE
WRF_MATGRP_STRUC
MANDT [CLNT (3)]
HIER_ID [CHAR (2)]
NODE [CHAR (18)]
DATE_FROM [DATS (8)]
0..N
WCB_COND_DISP-LTSNR_KG_KG = WYT1-LTSNR
WYT1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
LTSNR [CHAR (6)]
0..N