

SAP ABAP table /IPRO/TFILLIN {Association btwn TELM_VAR and TDOCSL}

/IPRO/TFILLIN-CMODIF = /IPRO/TCMODIF-CMODIF

0..N

_IPRO_TCMODIF	
<u>MANDT</u>	[CLNT (3)]
<u>CMODIF</u>	[CHAR (3)]
<u>CONTENT</u>	[CHAR (10)]

/IPRO/TFILLIN-CMODIFX = /IPRO/TCMODIF-CMODIF

0..N

_IPRO_TDOCSL	
<u>MANDT</u>	[CLNT (3)]
<u>CONTENT</u>	[CHAR (10)]
<u>DOCSL</u>	[CHAR (20)]

/IPRO/TFILLIN-DOCSL = /IPRO/TDOCSL-DOCSL

0..N

0..N, 1

_IPRO_TFILLIN	
<u>MANDT</u>	[CLNT (3)]
<u>CONTENT</u>	[CHAR (10)]
<u>VARB</u>	[CHAR (20)]
<u>CMODIF</u>	[CHAR (3)]
<u>ELMNTX</u>	[CHAR (20)]
<u>RGSETX</u>	[CHAR (10)]
<u>CMODIFX</u>	[CHAR (3)]
<u>EFFT_DTEX</u>	[DATS (8)]
<u>VERSIONX</u>	[NUMC (5)]
<u>DOCSL</u>	[CHAR (20)]
<u>OWNER</u>	[CHAR (20)]

/IPRO/TFILLIN-VERSIONX = /IPRO/TELMNT-EFFT_DTE

0..N

_IPRO_TELMNT	
<u>MANDT</u>	[CLNT (3)]
<u>CONTENT</u>	[CHAR (10)]
<u>ELMNT</u>	[CHAR (20)]
<u>RGSET</u>	[CHAR (10)]
<u>CMODIF</u>	[CHAR (3)]
<u>EFFT_DTE</u>	[DATS (8)]
<u>VERSION</u>	[NUMC (5)]

/IPRO/TFILLIN-OWNER = /IPRO/TOWNER-OWNER

_IPRO_TOWNER	
<u>MANDT</u>	[CLNT (3)]
<u>CONTENT</u>	[CHAR (10)]
<u>OWNER</u>	[CHAR (20)]

/IPRO/TFILLIN-RGSETX = /IPRO/TRGSET-RGSET

0..N

_IPRO_TRGSET	
<u>MANDT</u>	[CLNT (3)]
<u>CONTENT</u>	[CHAR (10)]
<u>RGSET</u>	[CHAR (10)]

/IPRO/TFILLIN-CONTENT = /IPRO/TVAR_CMP-CONTENT

0..N

_IPRO_TVAR_CMP	
<u>MANDT</u>	[CLNT (3)]
<u>CONTENT</u>	[CHAR (10)]
<u>VARB</u>	[CHAR (20)]
<u>CMODIF</u>	[CHAR (3)]

/IPRO/TFILLIN-MANDT = T000-MANDT

0..N

T000	
<u>MANDT</u>	[CLNT (3)]

0..N