

SAP ABAP table /ISDFPS/ME_NO_HEADER {DFPS: Notification Header - Mobile}

ISDFPS/ME_NO_HEADER

PLANPLANT [CHAR (4)]
EQUIPMENT [CHAR (18)]
ASSEMBLY [CHAR (18)]
UNIT [UNIT (3)]
PLANGROUP [CHAR (3)]
MNTPLAN [CHAR (12)]
MAINTITEM [CHAR (16)]
NOTIF_TYPE [CHAR (2)]
PRIOTYPE [CHAR (2)]
PRIORITY [CHAR (1)]
ORDERID [CHAR (12)]
MATERIAL [CHAR (18)]
CUST_NO [CHAR (10)]
OBJECT_NO [CHAR (22)]
CATPROFILE [CHAR (9)]
SALES_ORD [CHAR (10)]
DIVISION [CHAR (2)]
SALES_ORG [CHAR (4)]
DISTR_CHAN [CHAR (2)]
CAT_TYPE [CHAR (1)]
CODE_GROUP [CHAR (8)]
CODING [CHAR (4)]
PM_WKCTR [NUMC (8)]
SALES_OFFICE [CHAR (4)]
SALES_GRP [CHAR (3)]
NOTIFTMEZ [CHAR (6)]
FUNCT_LOC [CHAR (30)]
ABCINDIC [CHAR (1)]
MAINTPLANT [CHAR (4)]
MAINTLOC [CHAR (10)]
PLSECTN [CHAR (3)]
PP_WKCTR [NUMC (8)]
BUS_AREA [CHAR (4)]
CO_AREA [CHAR (4)]
COSTCENTER [CHAR (10)]
ASSET_NO [CHAR (12)]
SUB_NUMBER [CHAR (4)]
STDGORD [CHAR (12)]
STLMTORDER [CHAR (12)]
COMP_CODE [CHAR (4)]
SALES_ORG_LOC_ACC [CHAR (4)]
DIVISION_LOC_ACC [CHAR (2)]
DIST_CHAN_LOC_ACC [CHAR (2)]
DOC_NUMBER [CHAR (10)]
ITM_NUMBER [NUMC (6)]

Tables and Relationships:

- ANLA** (MANDT [CLNT (3)], BUKRS [CHAR (4)], ANLN1 [CHAR (12)], ANLN2 [CHAR (4)])
 - /ISDFPS/ME_NO_HEADER-SUB_NUMBER = ANLA-ANLN2 (0..N)
- ANLH** (MANDT [CLNT (3)], BUKRS [CHAR (4)], ANLN1 [CHAR (12)])
 - /ISDFPS/ME_NO_HEADER-ASSET_NO = ANLH-ANLN1 (0..N)
- AUFK** (MANDT [CLNT (3)], AUFNR [CHAR (12)])
 - /ISDFPS/ME_NO_HEADER-ORDERID = AUFK-AUFNR (0..N)
 - /ISDFPS/ME_NO_HEADER-STDGORD = AUFK-AUFNR (0..N)
 - /ISDFPS/ME_NO_HEADER-STLMTORDER = AUFK-AUFNR (0..N)
- CRID** (MANDT [CLNT (3)], OBJTY [CHAR (2)], OBJID [NUMC (8)])
 - /ISDFPS/ME_NO_HEADER-PM_WKCTR = CRID-OBJID (0..N)
 - /ISDFPS/ME_NO_HEADER-PP_WKCTR = CRID-OBJID (0..N)
- CSKS** (MANDT [CLNT (3)], KOKRS [CHAR (4)], KOSTL [CHAR (10)], DATB [DATS (8)])
 - /ISDFPS/ME_NO_HEADER-COSTCENTER = CSKS-KOSTL (0..N)
- EQUI** (MANDT [CLNT (3)], EQUNR [CHAR (18)])
 - /ISDFPS/ME_NO_HEADER-EQUIPMENT = EQUI-EQUNR (0..N)
- IFLOT** (MANDT [CLNT (3)], TPLNR [CHAR (30)])
 - /ISDFPS/ME_NO_HEADER-FUNCT_LOC = IFLOT-TPLNR (0..N)
- KNA1** (MANDT [CLNT (3)], KUNNR [CHAR (10)])
 - /ISDFPS/ME_NO_HEADER-CUST_NO = KNA1-KUNNR (0..N)
- MARA** (MANDT [CLNT (3)], MATNR [CHAR (18)])
 - /ISDFPS/ME_NO_HEADER-ASSEMBLY = MARA-MATNR (0..N)
 - /ISDFPS/ME_NO_HEADER-MATERIAL = MARA-MATNR (0..N)
- MPLA** (MANDT [CLNT (3)], WARPL [CHAR (12)])
 - /ISDFPS/ME_NO_HEADER-MNTPLAN = MPLA-WARPL (0..N)
- MPOS** (MANDT [CLNT (3)], WAPOS [CHAR (16)])
 - /ISDFPS/ME_NO_HEADER-MAINTITEM = MPOS-WAPOS (0..N)
- ONR00** (MANDT [CLNT (3)], OBJNR [CHAR (22)])
 - /ISDFPS/ME_NO_HEADER-OBJECT_NO = ONR00-OBJNR (0..N)
- QPCD** (MANDT [CLNT (3)], KATALOGART [CHAR (2)], CODEGRUPPE [CHAR (8)], CODE [CHAR (4)])
 - /ISDFPS/ME_NO_HEADER-CODING = QPCD-CODE (0..N)
- QPGR** (MANDT [CLNT (3)], KATALOGART [CHAR (2)], CODEGRUPPE [CHAR (8)])
 - /ISDFPS/ME_NO_HEADER-CODE_GROUP = QPGR-CODEGRUPPE (0..N)
- T001** (MANDT [CLNT (3)], BUKRS [CHAR (4)])
 - /ISDFPS/ME_NO_HEADER-COMP_CODE = T001-BUKRS (0..N)
- T001W** (MANDT [CLNT (3)], WERKS [CHAR (4)])
 - /ISDFPS/ME_NO_HEADER-MAINTPLANT = T001W-WERKS (0..N)
- T006** (MANDT [CLNT (3)], MSEHI [UNIT (3)])
 - /ISDFPS/ME_NO_HEADER-UNIT = T006-MSEHI (0..N)
- T024I** (MANDT [CLNT (3)], IWERK [CHAR (4)], INGRP [CHAR (3)])
 - /ISDFPS/ME_NO_HEADER-PLANGROUP = T024I-INGRP (0..N)
- T352B** (MANDT [CLNT (3)], RBNR [CHAR (9)])
 - /ISDFPS/ME_NO_HEADER-CATPROFILE = T352B-RBNR (0..N)
 - /ISDFPS/ME_NO_HEADER-PRIORITY = T356-PRIOK (0..N)
- T356** (MANDT [CLNT (3)], ARTPR [CHAR (2)], PRIOK [CHAR (1)])
 - /ISDFPS/ME_NO_HEADER-PRIOTYPE = T356A-ARTPR (0..N)
- T356A** (MANDT [CLNT (3)], ARTPR [CHAR (2)])
 - /ISDFPS/ME_NO_HEADER-PLSECTN = T357-BEBER (0..N)
- T357** (MANDT [CLNT (3)], WERKS [CHAR (4)], BEBER [CHAR (3)])
 - /ISDFPS/ME_NO_HEADER-ABCINDIC = T370C-ABCKZ (0..N)
- T370C** (MANDT [CLNT (3)], ABCKZ [CHAR (1)])
 - /ISDFPS/ME_NO_HEADER-PLANPLANT = T399I-IWERK (0..N)
- T399I** (MANDT [CLNT (3)], IWERK [CHAR (4)])
 - /ISDFPS/ME_NO_HEADER-MAINTLOC = T499S-STAND (0..N)
- T499S** (MANDT [CLNT (3)], WERKS [CHAR (4)], STAND [CHAR (10)])
 - /ISDFPS/ME_NO_HEADER-BUS_AREA = TGSB-GSBER (0..N)
- TGSB** (MANDT [CLNT (3)], GSBER [CHAR (4)])
 - /ISDFPS/ME_NO_HEADER-CO_AREA = TKA01-KOKRS (0..N)
- TKA01** (MANDT [CLNT (3)], KOKRS [CHAR (4)])
 - /ISDFPS/ME_NO_HEADER-CAT_TYPE = TQ15-KATALOGART (0..N)
- TQ15** (MANDT [CLNT (3)], KATALOGART [CHAR (2)])
 - /ISDFPS/ME_NO_HEADER-NOTIF_TYPE = TQ80-QMART (0..N)
- TQ80** (MANDT [CLNT (3)], QMART [CHAR (2)])
 - /ISDFPS/ME_NO_HEADER-DIVISION = TSPA-SPART (0..N)
 - /ISDFPS/ME_NO_HEADER-DIVISION_LOC_ACC = TSPA-SPART (0..N)
- TSPA** (MANDT [CLNT (3)], SPART [CHAR (2)])
 - /ISDFPS/ME_NO_HEADER-NOTIFTMEZ = TTZZ-TZONE (0..N)
- TTZZ** (CLIENT [CLNT (3)], TZONE [CHAR (6)])
 - /ISDFPS/ME_NO_HEADER-SALES_OFFICE = TVBUR-VKBUR (0..N)
- TVBUR** (MANDT [CLNT (3)], VKBUR [CHAR (4)])
 - /ISDFPS/ME_NO_HEADER-SALES_GRP = TVKGR-VKGRP (0..N)
 - /ISDFPS/ME_NO_HEADER-SALES_ORG = TVKO-VKORG (0..N)
 - /ISDFPS/ME_NO_HEADER-SALES_ORG_LOC_ACC = TVKO-VKORG (0..N)
- TVKGR** (MANDT [CLNT (3)], VKGRP [CHAR (3)])
 - /ISDFPS/ME_NO_HEADER-DISTR_CHAN = TVTW-VTWEG (0..N)
- TVKO** (MANDT [CLNT (3)], VKORG [CHAR (4)])
 - /ISDFPS/ME_NO_HEADER-DIST_CHAN_LOC_ACC = TVTW-VTWEG (0..N)
- TVTW** (MANDT [CLNT (3)], VTWEG [CHAR (2)])
 - /ISDFPS/ME_NO_HEADER-DOC_NUMBER = VBUK-VBELN (0..N)
 - /ISDFPS/ME_NO_HEADER-SALES_ORD = VBUK-VBELN (0..N)
- VBUK** (MANDT [CLNT (3)], VBELN [CHAR (10)])
 - /ISDFPS/ME_NO_HEADER-ITM_NUMBER = VBUP-POSNR (0..N)
- VBUP** (MANDT [CLNT (3)], VBELN [CHAR (10)], POSNR [NUMC (6)])
 -