

SAP ABAP table /ISDFPS/NOTIF_HEADER {Test}

_ISDFPS_NOTIF_HEADER	
PLANPLANT	[CHAR (4)]
EQUIPMENT	[CHAR (18)]
ASSEMBLY	[CHAR (18)]
UNIT	[UNIT (3)]
PLANGROUP	[CHAR (3)]
MNTPLAN	[CHAR (12)]
MAINTITEM	[CHAR (16)]
NOTIF_TYPE	[CHAR (2)]
PRIOTYPE	[CHAR (2)]
PRIORITY	[CHAR (1)]
ORDERID	[CHAR (12)]
MATERIAL	[CHAR (18)]
CUST_NO	[CHAR (10)]
OBJECT_NO	[CHAR (22)]
CATPROFILE	[CHAR (9)]
SALES_ORD	[CHAR (10)]
DIVISION	[CHAR (2)]
SALES_ORG	[CHAR (4)]
DISTR_CHAN	[CHAR (2)]
CAT_TYPE	[CHAR (1)]
CODE_GROUP	[CHAR (8)]
CODING	[CHAR (4)]
PM_WKCTR	[NUMC (8)]
SALES_OFFICE	[CHAR (4)]
SALES_GRP	[CHAR (3)]
NOTIFMEZ	[CHAR (6)]
FUNCT_LOC	[CHAR (30)]
ABCINDIC	[CHAR (1)]
MAINTPLANT	[CHAR (4)]
MAINTLOC	[CHAR (10)]
PLSECTN	[CHAR (3)]
PP_WKCTR	[NUMC (8)]
BUS_AREA	[CHAR (4)]
CO_AREA	[CHAR (4)]
COSTCENTER	[CHAR (10)]
ASSET_NO	[CHAR (12)]
SUB_NUMBER	[CHAR (4)]
STDGORD	[CHAR (12)]
STLMTORDER	[CHAR (12)]
COMP_CODE	[CHAR (4)]
SALES_ORG_LOC_ACC	[CHAR (4)]
DIVISION_LOC_ACC	[CHAR (2)]
DIST_CHAN_LOC_ACC	[CHAR (2)]
DOC_NUMBER	[CHAR (10)]
ITM_NUMBER	[NUMC (6)]

/ISDFPS/NOTIF_HEADER-SUB_NUMBER = ANLA-ANLN2

ANLA
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]
ANLN2 [CHAR (4)]

/ISDFPS/NOTIF_HEADER-ASSET_NO = ANLH-ANLN1

ANLH
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]

/ISDFPS/NOTIF_HEADER-ORDERID = AUFK-AUFNR

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

/ISDFPS/NOTIF_HEADER-STDGORD = AUFK-AUFNR

/ISDFPS/NOTIF_HEADER-STLMTORDER = AUFK-AUFNR

CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

/ISDFPS/NOTIF_HEADER-PM_WKCTR = CRID-OBJID

/ISDFPS/NOTIF_HEADER-PP_WKCTR = CRID-OBJID

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

/ISDFPS/NOTIF_HEADER-COSTCENTER = CSKS-KOSTL

/ISDFPS/NOTIF_HEADER-EQUIPMENT = EQUI-EQUNR

EQUI
MANDT [CLNT (3)]
EQUNR [CHAR (18)]

/ISDFPS/NOTIF_HEADER-FUNCT_LOC = IFLOT-TPLNR

IFLOT
MANDT [CLNT (3)]
TPLNR [CHAR (30)]

/ISDFPS/NOTIF_HEADER-CUST_NO = KNA1-KUNNR

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

/ISDFPS/NOTIF_HEADER-ASSEMBLY = MARA-MATNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

/ISDFPS/NOTIF_HEADER-MATERIAL = MARA-MATNR

/ISDFPS/NOTIF_HEADER-MNTPLAN = MPLA-WARPL

MPLA
MANDT [CLNT (3)]
WARPL [CHAR (12)]

/ISDFPS/NOTIF_HEADER-MAINTITEM = MPOS-WAPOS

MPOS
MANDT [CLNT (3)]
WAPOS [CHAR (16)]

/ISDFPS/NOTIF_HEADER-OBJECT_NO = ONR00-OBJNR

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

/ISDFPS/NOTIF_HEADER-CODING = QPCD-CODE

QPCD
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]
CODEGRUPPE [CHAR (8)]
CODE [CHAR (4)]

/ISDFPS/NOTIF_HEADER-CODE_GROUP = QPGR-CODEGRUPPE

QPGR
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]
CODEGRUPPE [CHAR (8)]

/ISDFPS/NOTIF_HEADER-COMP_CODE = T001-BUKRS

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

/ISDFPS/NOTIF_HEADER-MAINTPLANT = T001W-WERKS

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

/ISDFPS/NOTIF_HEADER-UNIT = T006-MSEHI

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

/ISDFPS/NOTIF_HEADER-PLANGROUP = T024I-INGRP

T024I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
INGRP [CHAR (3)]

/ISDFPS/NOTIF_HEADER-CATPROFILE = T352B-RBNR

T352B
MANDT [CLNT (3)]
RBNR [CHAR (9)]

/ISDFPS/NOTIF_HEADER-PRIORITY = T356-PRIOK

T356
MANDT [CLNT (3)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]

/ISDFPS/NOTIF_HEADER-PRIOTYPE = T356A-ARTPR

T356A
MANDT [CLNT (3)]
ARTPR [CHAR (2)]

/ISDFPS/NOTIF_HEADER-PLSECTN = T357-BEBER

T357
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BEBER [CHAR (3)]

/ISDFPS/NOTIF_HEADER-ABCINDIC = T370C-ABCKZ

T370C
MANDT [CLNT (3)]
ABCKZ [CHAR (1)]

/ISDFPS/NOTIF_HEADER-PLANPLANT = T399I-IWERK

T399I
MANDT [CLNT (3)]
IWERK [CHAR (4)]

/ISDFPS/NOTIF_HEADER-MAINTLOC = T499S-STAND

T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

/ISDFPS/NOTIF_HEADER-BUS_AREA = TGSB-GSBER

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

/ISDFPS/NOTIF_HEADER-CO_AREA = TKA01-KOKRS

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

/ISDFPS/NOTIF_HEADER-CAT_TYPE = TQ15-KATALOGART

TQ15
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]

/ISDFPS/NOTIF_HEADER-NOTIF_TYPE = TQ80-QMART

TQ80
MANDT [CLNT (3)]
QMART [CHAR (2)]

/ISDFPS/NOTIF_HEADER-DIVISION = TSPA-SPART

TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]

/ISDFPS/NOTIF_HEADER-DIVISION_LOC_ACC = TSPA-SPART

TTZZ
CLIENT [CLNT (3)]
TZONE [CHAR (6)]

/ISDFPS/NOTIF_HEADER-NOTIFTIMEZ = TTZZ-TZONE

TVBUR
MANDT [CLNT (3)]
VKBUR [CHAR (4)]

/ISDFPS/NOTIF_HEADER-SALES_OFFICE = TVBUR-VKBUR

TVKGR
MANDT [CLNT (3)]
VKGRP [CHAR (3)]

/ISDFPS/NOTIF_HEADER-SALES_GRP = TVKGR-VKGRP

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]

/ISDFPS/NOTIF_HEADER-SALES_ORG = TVKO-VKORG

TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]

/ISDFPS/NOTIF_HEADER-SALES_ORG_LOC_ACC = TVKO-VKORG

/ISDFPS/NOTIF_HEADER-DISTR_CHAN = TVTW-VTWEG

/ISDFPS/NOTIF_HEADER-DIST_CHAN_LOC_ACC = TVTW-VTWEG

/ISDFPS/NOTIF_HEADER-DOC_NUMBER = VBUK-VBELN

VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]

/ISDFPS/NOTIF_HEADER-SALES_ORD = VBUK-VBELN

/ISDFPS/NOTIF_HEADER-ITM_NUMBER = VBUP-POSNR

VBUP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]