

SAP ABAP table /RPM/TS_ITEM_T_DASH_ATT {Data Fields of Dashboard}

/RPM/TS_ITEM_T_DASH_ATT-UNIT = /RPM/CAP_UNITS-UNIT

_RPM_TS_ITEM_T_DASH_ATT	
CATEGORY [NUMC (4)]	
SUBCATEGORY [NUMC (4)]	
PTYPE [NUMC (4)]	
TTYPE [NUMC (4)]	
CURRENCY [CUKY (5)]	
PERIODTYPE [NUMC (2)]	
UNIT [UNIT (3)]	
PRIORITY_GROUP [NUMC (2)]	
CAP_PERIODTYPE [NUMC (2)]	
LOCATION [CHAR (4)]	
GEOGRAPHY [CHAR (4)]	

_RPM_CAP_UNITS	
CLIENT [CLNT (3)]	
UNIT [UNIT (3)]	

_RPM_CURRENCY	
CLIENT [CLNT (3)]	
CURRENCY [CUKY (5)]	

_RPM_PERIOD_TYPE	
CLIENT [CLNT (3)]	
PERIODTYPE [NUMC (2)]	

DPR_AREA	
MANDT [CLNT (3)]	
AREA [CHAR (4)]	

DPR_LOCATION	
MANDT [CLNT (3)]	
LOCATION [CHAR (4)]	

RPM_PROJ_CAT	
MANDT [CLNT (3)]	
CATEGORY [NUMC (4)]	

RPM_PROJ_PRGRP	
MANDT [CLNT (3)]	
PRIORITY_GROUP [NUMC (2)]	

RPM_PROJ_SUBCAT	
MANDT [CLNT (3)]	
CATEGORY [NUMC (4)]	
SUBCATEGORY [NUMC (4)]	

RPM_PROJ_TTYPE	
MANDT [CLNT (3)]	
CATEGORY [NUMC (4)]	
TTYPE [NUMC (4)]	

RPM_PROJ_TYPE	
MANDT [CLNT (3)]	
CATEGORY [NUMC (4)]	
PTYPE [NUMC (4)]	

