

SAP ABAP table /SAPSMOSS/RQMQMEL1 {R/3 Notifications (Reporting)}

/SAPSMOSS/RQMQMEL1-/SAPSMOSS/ADDID = /SAPSMOSS/ADDID-R3ADDID

<u>_SAPSMOSS_ADDID</u>
MANDT [CLNT (3)]
R3ADDID [CHAR (10)]

/SAPSMOSS/RQMQMEL1-/SAPSMOSS/ADDREL = /SAPSMOSS/ADDRL-R3ADDREL

<u>_SAPSMOSS_ADDRL</u>
MANDT [CLNT (3)]
R3ADDREL [CHAR (10)]

/SAPSMOSS/RQMQMEL1-/SAPSMOSS/DBSYS = /SAPSMOSS/DBSY-DBSYS

<u>_SAPSMOSS_DBSY</u>
MANDT [CLNT (3)]
DBSYS [CHAR (10)]

/SAPSMOSS/RQMQMEL1-/SAPSMOSS/FRONT = /SAPSMOSS/FRNT-FRONTEND

<u>_SAPSMOSS_FRNT</u>
MANDT [CLNT (3)]
FRONTEND [CHAR (10)]

/SAPSMOSS/RQMQMEL1-/SAPSMOSS/INSTN = /SAPSMOSS/INSTN-R3INSTN

<u>_SAPSMOSS_INSTN</u>
MANDT [CLNT (3)]
R3INSTN [CHAR (10)]

/SAPSMOSS/RQMQMEL1-/SAPSMOSS/OSSYS = /SAPSMOSS/OSYS-OSSYS

<u>_SAPSMOSS_OSYS</u>
MANDT [CLNT (3)]
OSSYS [CHAR (10)]

/SAPSMOSS/RQMQMEL1-/SAPSMOSS/REL = /SAPSMOSS/REL-R3REL

<u>_SAPSMOSS_REL</u>
MANDT [CLNT (3)]
R3REL [CHAR (10)]

/SAPSMOSS/RQMQMEL1-/SAPSMOSS/STATUS = /SAPSMOSS/STAT-STATUS

<u>_SAPSMOSS_STAT</u>
STATUS [CHAR (1)]

/SAPSMOSS/RQMQMEL1-/SAPSMOSS/SYSTYP = /SAPSMOSS/SYST-R3SYSTYPE

<u>_SAPSMOSS_SYST</u>
MANDT [CLNT (3)]
R3SYSTYPE [CHAR (1)]

/SAPSMOSS/RQMQMEL1-AUFNR = AUFK-AUFNR

<u>AUFK</u>
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

/SAPSMOSS/RQMQMEL1-COAFNR = AUFK-AUFNR

/SAPSMOSS/RQMQMEL1-FERTAUFNR = AUFK-AUFNR

/SAPSMOSS/RQMQMEL1-ARBPL = CRID-OBJID

<u>CRID</u>
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

/SAPSMOSS/RQMQMEL1-EBELN = EKKO-EBELN

<u>EKKO</u>
MANDT [CLNT (3)]
EBELN [CHAR (10)]

/SAPSMOSS/RQMQMEL1-EBELP = EKPO-EBELP

<u>EKPO</u>
MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]

/SAPSMOSS/RQMQMEL1-KUNUM = KNA1-KUNNR

<u>KNA1</u>
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

/SAPSMOSS/RQMQMEL1-HERSTELLER = LFA1-LIFNR

<u>LFA1</u>
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

/SAPSMOSS/RQMQMEL1-LIFNUM = LFA1-LIFNR

<u>MARA</u>
MANDT [CLNT (3)]
MATNR [CHAR (18)]

/SAPSMOSS/RQMQMEL1-EMATNR = MARA-MATNR

/SAPSMOSS/RQMQMEL1-MATNR = MARA-MATNR

/SAPSMOSS/RQMQMEL1-CHARG = MCH1-CHARG

<u>MCH1</u>
MANDT [CLNT (3)]
MATNR [CHAR (18)]
CHARG [CHAR (10)]

/SAPSMOSS/RQMQMEL1-RM_MATNR = MKAL-MATNR

<u>MKAL</u>
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
VERID [CHAR (4)]

/SAPSMOSS/RQMQMEL1-RM_WERKS = MKAL-WERKS

/SAPSMOSS/RQMQMEL1-VERID = MKAL-VERID

/SAPSMOSS/RQMQMEL1-OBJNR = ONR00-OBJNR

<u>ONR00</u>
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

/SAPSMOSS/RQMQMEL1-PRUEFLOS = QALS-PRUEFLOS

<u>QALS</u>
MANDANT [CLNT (3)]
PRUEFLOS [NUMC (12)]

/SAPSMOSS/RQMQMEL1-QWRNUM = QMEL-QMNUM

/SAPSMOSS/RQMQMEL1-QMGRP = QPGR-CODEGRUPPE

<u>QMEL</u>
MANDT [CLNT (3)]
QMNUM [CHAR (12)]

/SAPSMOSS/RQMQMEL1-MANDT = T000-MANDT

<u>QPGR</u>
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]
CODEGRUPPE [CHAR (8)]

/SAPSMOSS/RQMQMEL1-LGORTCHARG = T001L-LGORT

<u>T000</u>
MANDT [CLNT (3)]

/SAPSMOSS/RQMQMEL1-LGORTVORG = T001L-LGORT

/SAPSMOSS/RQMQMEL1-ARBPLWERK = T001W-WERKS

<u>T001L</u>
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]

/SAPSMOSS/RQMQMEL1-MAWERK = T001W-WERKS

<u>T001W</u>
MANDT [CLNT (3)]
WERKS [CHAR (4)]

/SAPSMOSS/RQMQMEL1-COUNTRY = T005-LAND1

<u>T005</u>
MANDT [CLNT (3)]
LAND1 [CHAR (3)]

/SAPSMOSS/RQMQMEL1-REGION = T005S-BLAND

<u>T005S</u>
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]

/SAPSMOSS/RQMQMEL1-MARBEH = T006-MSEHI

<u>T006</u>
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

/SAPSMOSS/RQMQMEL1-BKGRP = T024-EKGRP

<u>T024</u>
MANDT [CLNT (3)]
EKGRP [CHAR (3)]

/SAPSMOSS/RQMQMEL1-EKORG = T024E-EKORG

<u>T024E</u>
MANDT [CLNT (3)]
EKORG [CHAR (4)]

/SAPSMOSS/RQMQMEL1-RBNR = T352B-RBNR

<u>T352B</u>
MANDT [CLNT (3)]
RBNR [CHAR (9)]

/SAPSMOSS/RQMQMEL1-PRIOK = T356-PRIOK

<u>T356</u>
MANDT [CLNT (3)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]

/SAPSMOSS/RQMQMEL1-ARTPR = T356A-ARTPR

<u>T356A</u>
MANDT [CLNT (3)]
ARTPR [CHAR (2)]

/SAPSMOSS/RQMQMEL1-WAERS = TCURC-WAERS

<u>TCURC</u>
MANDT [CLNT (3)]
WAERS [CUKY (5)]

/SAPSMOSS/RQMQMEL1-QMKAT = TQ15-KATALOGART

<u>TQ15</u>
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]

/SAPSMOSS/RQMQMEL1-QMART = TQ80-QMART

<u>TQ80</u>
MANDT [CLNT (3)]
QMART [CHAR (2)]

/SAPSMOSS/RQMQMEL1-FEART = TQ86-FEART

<u>TQ86</u>
MANDT [CLNT (3)]
FEART [CHAR (8)]

/SAPSMOSS/RQMQMEL1-SPART = TSPA-SPART

<u>TSPA</u>
MANDT [CLNT (3)]
SPART [CHAR (2)]

/SAPSMOSS/RQMQMEL1-VKORG = TVKO-VKORG

<u>TVKO</u>
MANDT [CLNT (3)]
VKORG [CHAR (4)]

/SAPSMOSS/RQMQMEL1-VTWEG = TVTW-VTWEG

<u>TVTW</u>
MANDT [CLNT (3)]
VTWEG [CHAR (2)]

/SAPSMOSS/RQMQMEL1-LS_KDAUF = VBUK-VBELN

/SAPSMOSS/RQMQMEL1-LS_VBELN = VBUK-VBELN

/SAPSMOSS/RQMQMEL1-VBELN = VBUK-VBELN

<u>VBUK</u>
MANDT [CLNT (3)]
VBELN [CHAR (10)]

/SAPSMOSS/RQMQMEL1-LS_POSNR = VBUP-POSNR

<u>VBUP</u>
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]

<u>_SAPSMOSS_RQMQMEL1</u>
MANDT [CLNT (3)]
QMNUM [CHAR (12)]
QMART [CHAR (2)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]
WAERS [CUKY (5)]
AUFNR [CHAR (12)]
VERID [CHAR (4)]
RM_MATNR [CHAR (18)]
RM_WERKS [CHAR (4)]
MATNR [CHAR (18)]
KUNUM [CHAR (10)]
OBJNR [CHAR (22)]
RBNR [CHAR (9)]
LIFNUM [CHAR (10)]
VBELN [CHAR (10)]
SPART [CHAR (2)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
MAWERK [CHAR (4)]
QMKAT [CHAR (1)]
QMGRP [CHAR (8)]
PRUEFLOS [NUMC (12)]
CHARG [CHAR (10)]
LGORTCHARG [CHAR (4)]
HERSTELLER [CHAR (10)]
EMATNR [CHAR (18)]
EKORG [CHAR (4)]
BKGRP [CHAR (3)]
LGORTVORG [CHAR (4)]
FERTAUFNR [CHAR (12)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
LS_KDAUF [CHAR (10)]
LS_VBELN [CHAR (10)]
LS_POSNR [NUMC (6)]
ARBPL [NUMC (8)]
ARBPLWERK [CHAR (4)]
FEART [CHAR (8)]
MGEIN [UNIT (3)]
COAFNR [CHAR (12)]
QWRNUM [CHAR (12)]
MARBEH [UNIT (3)]
COUNTRY [CHAR (3)]
REGION [CHAR (3)]
_SAPSMOSS_INSTN [CHAR (10)]
_SAPSMOSS_OSSYS [CHAR (10)]
_SAPSMOSS_DBSYS [CHAR (10)]
_SAPSMOSS_REL [CHAR (10)]
_SAPSMOSS_FRONT [CHAR (10)]
_SAPSMOSS_SYSTYP [CHAR (1)]
_SAPSMOSS_ADDID [CHAR (10)]
_SAPSMOSS_ADDREL [CHAR (10)]
_SAPSMOSS_STATUS [CHAR (1)]
_SAPSMOSS_SYST [CHAR (1)]