

SAP ABAP table /SAPSRM/V_MDFSBC_ANY {Generated Table for View}

/SAPSRM/V_MDFSBC_ANY-ENABLED = /SAPSRM/C_FLG_2-XFIELD2

0..N

_SAPSRM_C_FLG_2
<u>XFIELD2</u> [CHAR (1)]

/SAPSRM/V_MDFSBC_ANY-REQUIRED = /SAPSRM/C_FLG_3-XFIELD3

0..N

_SAPSRM_C_FLG_3
<u>XFIELD3</u> [CHAR (1)]

/SAPSRM/V_MDFSBC_ANY-VISIBLE = /SAPSRM/C_FLG_D-XFIELD

0..N

_SAPSRM_C_FLG_D
<u>XFIELD</u> [CHAR (1)]

/SAPSRM/V_MDFSBC_ANY-ENTRY_TYPE = /SAPSRM/C_MDFET-ENTRY_TYPE

0..N

_SAPSRM_C_MDFET
<u>ENTRY_TYPE</u> [CHAR (1)]

/SAPSRM/V_MDFSBC_ANY-BUS_OBJ_TYPE = /SAPSRM/C_OBJTY-OBJECT_TYPE

0..N

_SAPSRM_C_OBJTY
<u>OBJECT_TYPE</u> [CHAR (10)]

/SAPSRM/V_MDFSBC_ANY-SET_LEVEL = /SAPSRM/C_SETLV-SET_LEVEL

0..N

_SAPSRM_C_SETLV
<u>SET_LEVEL</u> [CHAR (6)]

/SAPSRM/V_MDFSBC_ANY-SET_TYPE = /SAPSRM/C_SETTY-SET_TYPE

0..N

_SAPSRM_C_SETTY
<u>SET_TYPE</u> [CHAR (5)]
<u>SET_TYPE_LONG</u> [CHAR (20)]

/SAPSRM/V_MDFSBC_ANY-FIELD_NAME = DD03L-FIELDNAME

0..N

DD03L
<u>TABNAME</u> [CHAR (30)]
<u>FIELDNAME</u> [CHAR (30)]
<u>AS4LOCAL</u> [CHAR (1)]
<u>AS4VERS</u> [NUMC (4)]
<u>POSITION</u> [NUMC (4)]

/SAPSRM/V_MDFSBC_ANY-DYN_CTRL_CU_CLAS = SEOCCLASS-CLSNAME

0..N

SEOCCLASS
<u>CLSNAME</u> [CHAR (30)]

_SAPSRM_V_MDFSBC_ANY
<u>CLIENT</u> [CLNT (3)]
<u>SET_TYPE</u> [CHAR (5)]
<u>FIELD_NAME</u> [CHAR (30)]
<u>BUS_OBJ_TYPE</u> [CHAR (10)]
<u>SET_LEVEL</u> [CHAR (6)]
<u>ENTRY_TYPE</u> [CHAR (1)]
<u>VISIBLE</u> [CHAR (1)]
<u>ENABLED</u> [CHAR (1)]
<u>REQUIRED</u> [CHAR (1)]
<u>DYN_CTRL_CU_CLAS</u> [CHAR (30)]

1

1

1

1

{0,1}

{0,1}

1

{0,1}

{0,1}

0..N