

SAP ABAP table BAPI2080_NOTHDRE {BAPI Service Notification Header}

BAPI2080_NOTHDRE-SUB_NUMBER = ANLA-ANLN2

ANLA
<i>MANDT</i> [CLNT (3)]
<i>BUKRS</i> [CHAR (4)]
<i>ANLN1</i> [CHAR (12)]
<i>ANLN2</i> [CHAR (4)]

BAPI2080_NOTHDRE-ASSET NO = ANLH-ANLN1

ANLH
<i>MANDT</i> [CLNT (3)]
<i>BUKRS</i> [CHAR (4)]
<i>ANLN1</i> [CHAR (12)]

BAPI2080_NOTHDRE-ORDERID = AUFK-AUFNR

AUFK
<i>MANDT</i> [CLNT (3)]
<i>AUFNR</i> [CHAR (12)]

BAPI2080_NOTHDRE-STDGORD = AUFK-AUFNR

CRID
<i>MANDT</i> [CLNT (3)]
<i>OBJTY</i> [CHAR (2)]
<i>OBJID</i> [NUMC (8)]

BAPI2080_NOTHDRE-STLMTORDER = AUFK-AUFNR

BAPI2080_NOTHDRE-PM_WKCTR = CRID-OBJID

BAPI2080_NOTHDRE-PP_WKCTR = CRID-OBJID

BAPI2080_NOTHDRE-COSTCENTER = CSKS-KOSTL

CSKS
<i>MANDT</i> [CLNT (3)]
<i>KOKRS</i> [CHAR (4)]
<i>KOSTL</i> [CHAR (10)]
<i>DATBI</i> [DATS (8)]

BAPI2080_NOTHDRE-FIRST_OFFSET_TYPE_CODE = EAML_D_OFFSET_TC-OFFSET_TC

EAML_D_OFFSET_TC
<i>MANDT</i> [CLNT (3)]
<i>OFFSET_TC</i> [CHAR (2)]

BAPI2080_NOTHDRE-SECOND_OFFSET_TYPE_CODE = EAML_D_OFFSET_TC-OFFSET_TC

BAPI2080_NOTHDRE-EQUIPMENT = EQUI-EQUNR

EQUI
<i>MANDT</i> [CLNT (3)]
<i>EQUNR</i> [CHAR (18)]

BAPI2080_NOTHDRE-FUNCT_LOC = IFLOT-TPLNR

IFLOT
<i>MANDT</i> [CLNT (3)]
<i>TPLNR</i> [CHAR (30)]

BAPI2080_NOTHDRE-CUST_NO = KNA1-KUNNR

KNA1
<i>MANDT</i> [CLNT (3)]
<i>KUNNR</i> [CHAR (10)]

BAPI2080_NOTHDRE-ASSEMBLY = MARA-MATNR

BAPI2080_NOTHDRE-MATERIAL = MARA-MATNR

MARA
<i>MANDT</i> [CLNT (3)]
<i>MATNR</i> [CHAR (18)]

BAPI2080_NOTHDRE-MNTPLAN = MPLA-WARPL

MPLA
<i>MANDT</i> [CLNT (3)]
<i>WARPL</i> [CHAR (12)]

BAPI2080_NOTHDRE-MAINTITEM = MPOS-WAPOS

MPOS
<i>MANDT</i> [CLNT (3)]
<i>WAPOS</i> [CHAR (16)]

BAPI2080_NOTHDRE-OBJECT NO = ONR00-OBJNR

ONR00
<i>MANDT</i> [CLNT (3)]
<i>OBJNR</i> [CHAR (22)]

BAPI2080_NOTHDRE-CODING = QPCD-CODE

QPCD
<i>MANDT</i> [CLNT (3)]
<i>KATALOGART</i> [CHAR (2)]
<i>CODEGRUPPE</i> [CHAR (8)]
<i>CODE</i> [CHAR (4)]

BAPI2080_NOTHDRE-CODE_GROUP = QPGR-CODEGRUPPE

QPGR
<i>MANDT</i> [CLNT (3)]
<i>KATALOGART</i> [CHAR (2)]
<i>CODEGRUPPE</i> [CHAR (8)]

BAPI2080_NOTHDRE-COMP_CODE = T001-BUKRS

T001
<i>MANDT</i> [CLNT (3)]
<i>BUKRS</i> [CHAR (4)]

BAPI2080_NOTHDRE-MAINTPLANT = T001W-WERKS

T001W
<i>MANDT</i> [CLNT (3)]
<i>WERKS</i> [CHAR (4)]

BAPI2080_NOTHDRE-FIRST_OFFSET_UNIT = T006-MSEHI

BAPI2080_NOTHDRE-LINEAR_UNIT = T006-MSEHI

BAPI2080_NOTHDRE-MARKER_DISTANCE_UNIT = T006-MSEHI

BAPI2080_NOTHDRE-SECOND_OFFSET_UNIT = T006-MSEHI

BAPI2080_NOTHDRE-UNIT = T006-MSEHI

T024I
<i>MANDT</i> [CLNT (3)]
<i>IWERK</i> [CHAR (4)]
<i>INGRP</i> [CHAR (3)]

BAPI2080_NOTHDRE-PLANGROUP = T024I-INGRP

BAPI2080_NOTHDRE-CATPROFILE = T352B-RBNR

T352B
<i>MANDT</i> [CLNT (3)]
<i>RBNR</i> [CHAR (9)]

BAPI2080_NOTHDRE-PRIORITY = T356-PRIOK

T356
<i>MANDT</i> [CLNT (3)]
<i>ARTPR</i> [CHAR (2)]
<i>PRIOK</i> [CHAR (1)]

BAPI2080_NOTHDRE-PRIOTYPE = T356A-ARTPR

T356A
<i>MANDT</i> [CLNT (3)]
<i>ARTPR</i> [CHAR (2)]

BAPI2080_NOTHDRE-PLSECTN = T357-BEBER

T357
<i>MANDT</i> [CLNT (3)]
<i>WERKS</i> [CHAR (4)]
<i>BEBER</i> [CHAR (3)]

BAPI2080_NOTHDRE-ABCINDIC = T370C-ABCKZ

T370C
<i>MANDT</i> [CLNT (3)]
<i>ABCKZ</i> [CHAR (1)]

BAPI2080_NOTHDRE-PLANPLANT = T399I-IWERK

T399I
<i>MANDT</i> [CLNT (3)]
<i>IWERK</i> [CHAR (4)]

BAPI2080_NOTHDRE-MAINTLOC = T499S-STAND

T499S
<i>MANDT</i> [CLNT (3)]
<i>WERKS</i> [CHAR (4)]
<i>STAND</i> [CHAR (10)]

BAPI2080_NOTHDRE-BUS_AREA = TGSB-GSBER

TGSB
<i>MANDT</i> [CLNT (3)]
<i>GSBER</i> [CHAR (4)]

BAPI2080_NOTHDRE-CO_AREA = TKA01-KOKRS

TKA01
<i>MANDT</i> [CLNT (3)]
<i>KOKRS</i> [CHAR (4)]

BAPI2080_NOTHDRE-CAT_TYPE = TQ15-KATALOGART

TQ15
<i>MANDT</i> [CLNT (3)]
<i>KATALOGART</i> [CHAR (2)]

BAPI2080_NOTHDRE-NOTIF_TYPE = TQ80-QMART

TQ80
<i>MANDT</i> [CLNT (3)]
<i>QMART</i> [CHAR (2)]

BAPI2080_NOTHDRE-DIVISION = TSPA-SPART

TSPA
<i>MANDT</i> [CLNT (3)]
<i>SPART</i> [CHAR (2)]

BAPI2080_NOTHDRE-NOTIFTMEZ = TTZZ-TZONE

TTZZ
<i>CLIENT</i> [CLNT (3)]
<i>TZONE</i> [CHAR (6)]

BAPI2080_NOTHDRE-SALES_OFFICE = TVBUR-VKBUR

TVBUR
<i>MANDT</i> [CLNT (3)]
<i>VKBUR</i> [CHAR (4)]

BAPI2080_NOTHDRE-SALES_GRP = TVKGR-VKGRP

TVKGR
<i>MANDT</i> [CLNT (3)]
<i>VKGRP</i> [CHAR (3)]

BAPI2080_NOTHDRE-SALES_ORG = TVKO-VKORG

TVKO
<i>MANDT</i> [CLNT (3)]
<i>VKORG</i> [CHAR (4)]

BAPI2080_NOTHDRE-DISTR_CHAN = TVTW-VTWEG

TVTW
<i>MANDT</i> [CLNT (3)]
<i>VTWEG</i> [CHAR (2)]

BAPI2080_NOTHDRE-DOC_NUMBER = VBUK-VBELN

VBUK
<i>MANDT</i> [CLNT (3)]
<i>VBELN</i> [CHAR (10)]

BAPI2080_NOTHDRE-SALES_ORD = VBUK-VBELN

VBUP
<i>MANDT</i> [CLNT (3)]
<i>VBELN</i> [CHAR (10)]
<i>POSNR</i> [NUMC (6)]

BAPI2080_NOTHDRE-ITM_NUMBER = VBUP-POSNR

BAPI2080_NOTHDRE
<i>PLANPLANT</i> [CHAR (4)]
<i>EQUIPMENT</i> [CHAR (18)]
<i>ASSEMBLY</i> [CHAR (18)]
<i>UNIT</i> [UNIT (3)]
<i>PLANGROUP</i> [CHAR (3)]
<i>MNTPLAN</i> [CHAR (12)]
<i>MAINTITEM</i> [CHAR (16)]
<i>NOTIF_TYPE</i> [CHAR (2)]
<i>PRIOTYPE</i> [CHAR (2)]
<i>PRIORITY</i> [CHAR (1)]
<i>ORDERID</i> [CHAR (12)]
<i>MATERIAL</i> [CHAR (18)]
<i>CUST_NO</i> [CHAR (10)]
<i>OBJECT_NO</i> [CHAR (22)]
<i>CATPROFILE</i> [CHAR (9)]
<i>SALES_ORD</i> [CHAR (10)]
<i>DIVISION</i> [CHAR (2)]
<i>SALES_ORG</i> [CHAR (4)]
<i>DISTR_CHAN</i> [CHAR (2)]
<i>CAT_TYPE</i> [CHAR (1)]
<i>CODE_GROUP</i> [CHAR (8)]
<i>CODING</i> [CHAR (4)]
<i>PM_WKCTR</i> [NUMC (8)]
<i>SALES_OFFICE</i> [CHAR (4)]
<i>SALES_GRP</i> [CHAR (3)]
<i>NOTIFTMEZ</i> [CHAR (6)]
<i>FUNCT_LOC</i> [CHAR (30)]
<i>ABCINDIC</i> [CHAR (1)]
<i>MAINTPLANT</i> [CHAR (4)]
<i>MAINTLOC</i> [CHAR (10)]
<i>PLSECTN</i> [CHAR (3)]
<i>PP_WKCTR</i> [NUMC (8)]
<i>BUS_AREA</i> [CHAR (4)]
<i>CO_AREA</i> [CHAR (4)]
<i>COSTCENTER</i> [CHAR (10)]
<i>ASSET_NO</i> [CHAR (12)]
<i>SUB_NUMBER</i> [CHAR (4)]
<i>STDGORD</i> [CHAR (12)]
<i>STLMTORDER</i> [CHAR (12)]
<i>COMP_CODE</i> [CHAR (4)]
<i>SALES_ORG_LOC_ACC</i> [CHAR (4)]
<i>DIVISION_LOC_ACC</i> [CHAR (2)]
<i>DIST_CHAN_LOC_ACC</i> [CHAR (2)]
<i>DOC_NUMBER</i> [CHAR (10)]
<i>ITM_NUMBER</i> [NUMC (6)]