

SAP ABAP table BAPI\_RE\_ARCH\_OBJECT\_DAT {Architectural Object - Data}

BAPI\_RE\_ARCH\_OBJECT\_DAT-HERITABLE\_BLDG\_RIGHT\_IND = TDO9-SOBJERBBAU

0..N

| TDO9                         |
|------------------------------|
| <u>MANDT</u> [CLNT (3)]      |
| <u>SOBJERBBAU</u> [CHAR (1)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-LOCATION = TIV10-SLAGewe

0..N

| TIV10                     |
|---------------------------|
| <u>MANDT</u> [CLNT (3)]   |
| <u>SLAGewe</u> [NUMC (4)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-MAINTENANCE AREA = TIV16-SINSTBEZ

0..N

| TIV16                      |
|----------------------------|
| <u>MANDT</u> [CLNT (3)]    |
| <u>SINSTBEZ</u> [NUMC (5)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-MAIN\_USAGE TYPE = TIV36-SUNART

0..N

| TIV36                    |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>SUNART</u> [CHAR (8)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-ELEVATOR\_TO FLOOR = TIV37-SSTOCKW

0..N

| TIV37                     |
|---------------------------|
| <u>MANDT</u> [CLNT (3)]   |
| <u>SSTOCKW</u> [NUMC (3)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-TOP\_FLOOR = TIV37-SSTOCKW

0..N

| TIV44                      |
|----------------------------|
| <u>MANDT</u> [CLNT (3)]    |
| <u>SVERKEHR</u> [CHAR (1)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-TRANSPORT\_CONNECTION = TIV44-SVERKEHR

0..N

BAPI\_RE\_ARCH\_OBJECT\_DAT-DISTRICT\_LOCATION = TIV45-SOBJLAGE

0..N

| TIV45                      |
|----------------------------|
| <u>MANDT</u> [CLNT (3)]    |
| <u>SOBJLAGE</u> [NUMC (2)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-PROPERTY\_TYPE = TIV56-SGRART

0..N

| TIV56                    |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>SGRART</u> [NUMC (4)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-LOCATION\_QUALITY = TIV57-SGRQAL

0..N

| TIV57                    |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>SGRQAL</u> [NUMC (3)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-GROUND\_TYPE = TIV58-SGRFRM

0..N

| TIV58                    |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>SGRFRM</u> [NUMC (3)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-OVERALL\_CONDITION = TIV59-SGRGZS

0..N

| TIV59                    |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>SGRGZS</u> [NUMC (3)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-BUILDING\_TYPE = TIV5A-SOBJART

0..N

| TIV5A                     |
|---------------------------|
| <u>MANDT</u> [CLNT (3)]   |
| <u>SOBJART</u> [NUMC (2)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-BUILDING\_CONDITION = TIV83-RZUSTAND

0..N

| TIV83                      |
|----------------------------|
| <u>MANDT</u> [CLNT (3)]    |
| <u>RZUSTAND</u> [NUMC (2)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-USAGE\_TYPE\_DEVELOPMENT\_PLAN = TIVB3-RNBPLAN

0..N

| TIVB3                     |
|---------------------------|
| <u>MANDT</u> [CLNT (3)]   |
| <u>RNBPLAN</u> [CHAR (4)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-FUNCTION = TIVBDARFUNC-AOFUNCTION

0..N

| TIVBDARFUNC                  |
|------------------------------|
| <u>MANDT</u> [CLNT (3)]      |
| <u>AOTYPE</u> [CHAR (4)]     |
| <u>AOFUNCTION</u> [CHAR (4)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-MEASUREMENT\_STRUCTURE = TIVBDMEASSTRC-MEASSTRC

0..N

| TIVBDMEASSTRC              |
|----------------------------|
| <u>MANDT</u> [CLNT (3)]    |
| <u>MEASSTRC</u> [CHAR (4)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-RESERVATION\_AREA = TIVORRSAREA-RSAREA

0..N

| TIVORRSAREA               |
|---------------------------|
| <u>MANDT</u> [CLNT (3)]   |
| <u>RSAREA</u> [CHAR (10)] |

BAPI\_RE\_ARCH\_OBJECT\_DAT-STAT\_PROF = TJ20-STSMA

0..N

| TJ20                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>STSMA</u> [CHAR (8)] |

| BAPI_RE_ARCH_OBJECT_DAT                       |
|-----------------------------------------------|
| <u>FUNCTION</u> [CHAR (4)]                    |
| <u>MEASUREMENT_STRUCTURE</u> [CHAR (4)]       |
| <u>MAINTENANCE_AREA</u> [NUMC (5)]            |
| <u>TRANSPORT_CONNECTION</u> [CHAR (1)]        |
| <u>LOCATION</u> [NUMC (4)]                    |
| <u>DISTRICT_LOCATION</u> [NUMC (2)]           |
| <u>PROPERTY_TYPE</u> [NUMC (4)]               |
| <u>LOCATION_QUALITY</u> [NUMC (3)]            |
| <u>GROUND_TYPE</u> [NUMC (3)]                 |
| <u>OVERALL_CONDITION</u> [NUMC (3)]           |
| <u>USAGE_TYPE_DEVELOPMENT_PLAN</u> [CHAR (4)] |
| <u>MAIN_USAGE_TYPE</u> [CHAR (8)]             |
| <u>HERITABLE_BLDG_RIGHT_IND</u> [CHAR (1)]    |
| <u>BUILDING_TYPE</u> [NUMC (2)]               |
| <u>BUILDING_CONDITION</u> [NUMC (2)]          |
| <u>TOP_FLOOR</u> [NUMC (3)]                   |
| <u>ELEVATOR_TO_FLOOR</u> [NUMC (3)]           |
| <u>STAT_PROF</u> [CHAR (8)]                   |
| <u>RESERVATION_AREA</u> [CHAR (10)]           |

{0,1}

{0,1}

{0,1}

{0,1}

{0,1}

{0,1}

{0,1}

{0,1}

{0,1}

{0,1}

{0,1}

{0,1}

{0,1}

{0,1}

{0,1}