

# SAP ABAP table CMS\_STR\_ACR\_MAP\_GET\_MLT {MAPI: GET: Structure for aircraft details}

CMS\_STR\_ACR\_MAP\_GET\_MLT-ACR\_REGC = T005-LAND1

<b>CMS_STR_ACR_MAP_GET_MLT</b>
MOV_CATEGORY [CHAR (6)]
MOV_TYP [CHAR (6)]
MOV_LOC_DESC [CHAR (6)]
MOV_IDEN_TYP [CHAR (6)]
MOV_UOB [CHAR (6)]
MOV_MANU_CNTRY [CHAR (3)]
MOV_TYPE_FEAT [CHAR (6)]
ACR_REGC [CHAR (3)]
ACR_MTOW_UNT [UNIT (3)]
ACR_RATCLS [CHAR (6)]
SFTY_AMT_CURR [CUKY (5)]
LIQD_REASON [CHAR (6)]
LIQD_CURR [CUKY (5)]
EXP_PRCD_CURR [CUKY (5)]
BANK_CNTRY_LIQ [CHAR (3)]
NOM_VALUE_CURR [CUKY (5)]
AST_VALUE_CURR [CUKY (5)]
UNIT_OF_MEASURE [UNIT (3)]
PUR_PRICE_CURR [CUKY (5)]
UNIT_PRICE_CURR [CUKY (5)]
TYPE_STK_EXCH [CHAR (6)]
STK_EXCH_ID [CHAR (6)]
DET_CURR [CUKY (5)]
STOCK_UOM [UNIT (3)]

1/1/1 0..N

0..N

1

1

0..N

1

1

1

0..N

0..N

1

1

0..N

0..N

1

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-BANK\_CNTRY\_LIQ = T005-LAND1

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-MOV\_MANU\_CNTRY = T005-LAND1

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-ACR\_MTOW\_UNT = T006-MSEHI

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-STOCK\_UOM = T006-MSEHI

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-UNIT\_OF\_MEASURE = T006-MSEHI

0..N

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-ACR\_RATCLS = TCMS\_ATT\_ID\_TY-INDICATOR\_TYPE

CMS\_STR\_ACR\_MAP\_GET\_MLT-LIQD\_REASON = TCMS\_ATT\_ID\_TY-INDICATOR\_TYPE

CMS\_STR\_ACR\_MAP\_GET\_MLT-MOV\_IDEN\_TYP = TCMS\_ATT\_ID\_TY-INDICATOR\_TYPE

0..N

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-MOV\_LOC\_DESC = TCMS\_ATT\_ID\_TY-INDICATOR\_TYPE

0..N

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-MOV\_UOB = TCMS\_ATT\_ID\_TY-INDICATOR\_TYPE

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-STK\_EXCH\_ID = TCMS\_ATT\_ID\_TY-INDICATOR\_TYPE

0..N

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-TYPE\_STK\_EXCH = TCMS\_ATT\_ID\_TY-INDICATOR\_TYPE

CMS\_STR\_ACR\_MAP\_GET\_MLT-MOV\_TYP = TCMS\_MOV\_TYP-MOV\_CATEGORY

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-MOV\_TYPE\_FEAT = TCMS\_OMS\_FEAT-TYPE\_FEAT

CMS\_STR\_ACR\_MAP\_GET\_MLT-AST\_VALUE\_CURR = TCURC-WAERS

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-DET\_CURR = TCURC-WAERS

CMS\_STR\_ACR\_MAP\_GET\_MLT-EXP\_PRCD\_CURR = TCURC-WAERS

CMS\_STR\_ACR\_MAP\_GET\_MLT-LIQD\_CURR = TCURC-WAERS

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-NOM\_VALUE\_CURR = TCURC-WAERS

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-PUR\_PRICE\_CURR = TCURC-WAERS

0..N

CMS\_STR\_ACR\_MAP\_GET\_MLT-SFTY\_AMT\_CURR = TCURC-WAERS

CMS\_STR\_ACR\_MAP\_GET\_MLT-UNIT\_PRICE\_CURR = TCURC-WAERS

<b>T005</b>
MANDT [CLNT (3)]
LAND1 [CHAR (3)]

<b>T006</b>
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

<b>TCMS_ATT_ID_TY</b>
MANDT [CLNT (3)]
INDICATOR_ID [CHAR (6)]
INDICATOR_TYPE [CHAR (6)]

<b>TCMS_MOV_TYP</b>
MANDT [CLNT (3)]
MOV_CATEGORY [CHAR (6)]
MOV_TYP [CHAR (6)]

<b>TCMS_OMS_FEAT</b>
MANDT [CLNT (3)]
CATEGORYID [CHAR (6)]
TYPE_FEAT [CHAR (6)]

<b>TCURC</b>
MANDT [CLNT (3)]
WAERS [CUKY (5)]

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N