

SAP ABAP table EAML_S_NWM_OL_ALV {EAML: Structure for OL mass maintenance}

EAML_S_NWM_OL_ALV-OFFSET1_TYPEFO = EAML_D_OFFSET_TC-OFFSET_TC

EAML_S_NWM_OL_ALV-OFFSET1_TYPELO = EAML_D_OFFSET_TC-OFFSET_TC

EAML_S_NWM_OL_ALV-OFFSET1_TYPETO = EAML_D_OFFSET_TC-OFFSET_TC

EAML_S_NWM_OL_ALV-OFFSET2_TYPEFO = EAML_D_OFFSET_TC-OFFSET_TC

EAML S NWM OL ALV-OFFSET2 TYPELO = EAML D OFFSET TC-OFFSET TC

EAML S NWM OL ALV-OFFSET2 TYPETO = EAML D OFFSET TC-OFFSET TC

EAML S NWM OL ALV-EDGETYPELO = EAML EDGE TYPE-EDGETYPE

EAML S NWM OL ALV-NODETYPEFO = EAML NODE TYPE-NODETYPE

EAML S NWM OL ALV-NODETYPE TO = EAML NODE TYPE-NODETYPE

$$\text{EAML S NWM OL ALV-OL CONN POSFO} = \text{EAML OL POS-OL CONN POS}$$
$$\text{EAML S NWM OL ALV-OL CONN POSTO} = \text{EAML OL POS-OL CONN POS}$$

EAML S NWM OL ALV-EQKANT = EQUI-EQUNR

EAML S NWM OL ALV-EQNACH = EQUI-EQUNR

EAML_S_NWM_OL_ALV-EQVON = EQUI-EQUNR

EAML S NWM OL ALV-TPKANT = IFLOT-TPLNR

EAML S NWM OL ALV-TPNACH = IFLOT-TPLNR

EAML S NWM OL ALV-TPVON = IFLOT-TPLNR

EAML S NWM OL ALV-STATUS = ONR00-OBJNR

EAML S NWM OL ALV-MANDT = T000-MANDT

EAML S NWM OL ALV-MLANG = T002-SPRAS

EAML S NWM OL ALV-SPRAS = T002-SPRAS

EAML S NWM OL ALV-LINEAR UNITFO = T006-MSEHI

EAML S NWM OL ALV-LINEAR UNITLO = T006-MSEHI

EAML S NWM OL ALV-LINEAR UNITTO = T006-MSEHI

EAML S NWM OL ALV-OFFSET1 UNITFO = T006-MSEHI

EAML S NWM OL ALV-OFFSET1 UNITLO = T006-MSEHI

EAML S NWM OL ALV-OFFSET1 UNITTO = T006-MSEHI

EAML S NWM OL ALV-OFFSET2 UNITFO = T006-MSEHI

EAML S NWM OL ALV-OFFSET2 UNITLO = T006-MSEHI

FAML S NWM OL ALV-OFFSET2 UNITTO = T006-MSEHI

EAML S NWM OL ALV-BEGRU = T370B-BEGRU

EAML S NWM OL ALV-NETYP = T370N-NETYP

EAML S NWM OL ALV-NETID = T372I-NETID

EAML S NWM OL ALV-MEDIU = T372M-MEDIU

EAML_D_OFFSET_TC
<u>MANDT</u> [CLNT (3)]
<u>OFFSET_TC</u> [CHAR (2)]

EAML_EDGE_TYPE
<u>MANDT</u> [CLNT (3)]
<u>EDGETYPE</u> [CHAR (10)]

EAML_NODE_TYPE
<u>MANDT</u> [CLNT (3)]
<u>NODETYPE</u> [CHAR (10)]

EAML_OL_POS
<u>MANDT</u> [CLNT (3)]
<u>OL_CONN_POS</u> [CHAR (2)]

EQUI
<u>MANDT</u> [CLNT (3)]
<u>EQUNR</u> [CHAR (18)]

IFLOT
<u>MANDT</u> [CLNT (3)]
<u>TPLNR</u> [CHAR (30)]

ONR00
<u>MANDT</u> [CLNT (3)]
<u>OBJNR</u> [CHAR (22)]

T000
<u>MANDT</u> [CLNT (3)]

T002
<u>SPRAS</u> [LANG (1)]

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

T370B
<u>MANDT</u> [CLNT (3)]
<u>BEGRU</u> [CHAR (4)]

T370N
<u>MANDT</u> [CLNT (3)]
<u>NETYP</u> [CHAR (1)]

T372I
<u>MANDT</u> [CLNT (3)]
<u>NETID</u> [CHAR (8)]

T372M
<u>MANDT</u> [CLNT (3)]
<u>MEDIU</u> [CHAR (6)]