

SAP ABAP table EAMS_S_BO_EQUI_HEADER {Business Object Equipment - Header Data}

EAMS_S_BO_EQUI_HEADER
AUTHGRP [CHAR (4)]
OBJECTTYPE [CHAR (10)]
PLANPLANT [CHAR (4)]
PLANGROUP [CHAR (3)]
CATPROFILE [CHAR (9)]
ABCINDIC [CHAR (1)]
MAINTPLANT [CHAR (4)]
MAINTLOC [CHAR (10)]
PLSECTN [CHAR (3)]
BUS_AREA [CHAR (4)]
COSTCENTER [CHAR (10)]
COMP_CODE [CHAR (4)]
SALES_ORG [CHAR (4)]
DISTR_CHAN [CHAR (2)]
DIVISION [CHAR (2)]
SALES_OFF [CHAR (4)]
SALES_GRP [CHAR (3)]
LINEAR_UNIT [UNIT (3)]
FIRST_OFFSET_TYPE_CODE [CHAR (2)]
FIRST_OFFSET_UNIT [UNIT (3)]
SECOND_OFFSET_TYPE_CODE [CHAR (2)]
SECOND_OFFSET_UNIT [UNIT (3)]
LINEAR_REFERENCE_PATTERN [CHAR (10)]
MARKER_DISTANCE_UNIT [UNIT (3)]
EQUICATGRY [CHAR (1)]
SAFETY_CHAR [CHAR (1)]

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

EAML_D_LRP_HDR
MANDT [CLNT (3)]
LRPID [CHAR (10)]

EAML_D_OFFSET_TC
MANDT [CLNT (3)]
OFFSET_TC [CHAR (2)]

EAMWS_SAF_CHAR
MANDT [CLNT (3)]
SAFETY_CHAR [CHAR (1)]

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

T024I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
INGRP [CHAR (3)]

T352B
MANDT [CLNT (3)]
RBNR [CHAR (9)]

T357
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BEBER [CHAR (3)]

T370B
MANDT [CLNT (3)]
BEGRU [CHAR (4)]

T370C
MANDT [CLNT (3)]
ABCKZ [CHAR (1)]

T370K
MANDT [CLNT (3)]
EQART [CHAR (10)]

T370T
MANDT [CLNT (3)]
EQTYP [CHAR (1)]

T399I
MANDT [CLNT (3)]
IWERK [CHAR (4)]

T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]

TVBUR
MANDT [CLNT (3)]
VKBUR [CHAR (4)]

TVKGR
MANDT [CLNT (3)]
VKGRP [CHAR (3)]

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]

TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]

0..N0..N10..N0..N0..N

EAMS_S_BO_EQUI_HEADER-COSTCENTER = CSKS-KOSTL

EAMS_S_BO_EQUI_HEADER-LINEAR_REFERENCE_PATTERN = EAML_D_LRP_HDR-LRPID

EAMS_S_BO_EQUI_HEADER-FIRST_OFFSET_TYPE_CODE = EAML_D_OFFSET_TC-OFFSET_TC

EAMS_S_BO_EQUI_HEADER-SECOND_OFFSET_TYPE_CODE = EAML_D_OFFSET_TC-OFFSET_TC

EAMS_S_BO_EQUI_HEADER-SAFETY_CHAR = EAMWS_SAF_CHAR-SAFETY_CHAR

EAMS_S_BO_EQUI_HEADER-COMP_CODE = T001-BUKRS

EAMS_S_BO_EQUI_HEADER-MAINTPLANT = T001W-WERKS

EAMS_S_BO_EQUI_HEADER-FIRST_OFFSET_UNIT = T006-MSEHI

EAMS_S_BO_EQUI_HEADER-LINEAR_UNIT = T006-MSEHI

EAMS_S_BO_EQUI_HEADER-MARKER_DISTANCE_UNIT = T006-MSEHI

EAMS_S_BO_EQUI_HEADER-SECOND_OFFSET_UNIT = T006-MSEHI

EAMS_S_BO_EQUI_HEADER-PLANGROUP = T024I-INGRP

EAMS_S_BO_EQUI_HEADER-CATPROFILE = T352B-RBNR

EAMS_S_BO_EQUI_HEADER-PLSECTN = T357-BEBER

EAMS_S_BO_EQUI_HEADER-AUTHGRP = T370B-BEGRU

EAMS_S_BO_EQUI_HEADER-ABCINDIC = T370C-ABCKZ

EAMS_S_BO_EQUI_HEADER-OBJECTTYPE = T370K-EQART

EAMS_S_BO_EQUI_HEADER-EQUICATGRY = T370T-EQTYP

EAMS_S_BO_EQUI_HEADER-PLANPLANT = T399I-IWERK

EAMS_S_BO_EQUI_HEADER-MAINTLOC = T499S-STAND

EAMS_S_BO_EQUI_HEADER-BUS_AREA = TGSB-GSBER

EAMS_S_BO_EQUI_HEADER-DIVISION = TSPA-SPART

EAMS_S_BO_EQUI_HEADER-SALES_OFF = TVBUR-VKBUR

EAMS_S_BO_EQUI_HEADER-SALES_GRP = TVKGR-VKGRP

EAMS_S_BO_EQUI_HEADER-SALES_ORG = TVKO-VKORG

EAMS_S_BO_EQUI_HEADER-DISTR_CHAN = TVTW-VTWEG