

EAMS_S_BO_NTF_HEADER	
PLANPLANT	[CHAR (4)]
EQUIPMENT	[CHAR (18)]
ASSEMBLY	[CHAR (18)]
UNIT	[UNIT (3)]
PLANGROUP	[CHAR (3)]
MNTPLAN	[CHAR (12)]
MAINTITEM	[CHAR (16)]
NOTIF_TYPE	[CHAR (2)]
PRIOTYPE	[CHAR (2)]
PRIORITY	[CHAR (1)]
ORDERID	[CHAR (12)]
MATERIAL	[CHAR (18)]
CUST_NO	[CHAR (10)]
OBJECT_NO	[CHAR (22)]
CATPROFILE	[CHAR (9)]
SALES_ORD	[CHAR (10)]
DIVISION	[CHAR (2)]
SALES_ORG	[CHAR (4)]
DISTR_CHAN	[CHAR (2)]
CAT_TYPE	[CHAR (1)]
CODE_GROUP	[CHAR (8)]
CODING	[CHAR (4)]
PM_WKCTR	[NUMC (8)]
SALES_OFFICE	[CHAR (4)]
SALES_GRP	[CHAR (3)]
NOTIFTMEZ	[CHAR (6)]
FUNCT_LOC	[CHAR (30)]
ABCDINDIC	[CHAR (1)]
MAINTPLANT	[CHAR (4)]
MAINTLOC	[CHAR (10)]
PLSECTN	[CHAR (3)]
PP_WKCTR	[NUMC (8)]
BUS_AREA	[CHAR (4)]
CO_AREA	[CHAR (4)]
COSTCENTER	[CHAR (10)]
ASSET_NO	[CHAR (12)]
SUB_NUMBER	[CHAR (4)]
STDGORD	[CHAR (12)]
STLMTORDER	[CHAR (12)]
COMP_CODE	[CHAR (4)]
SALES_ORG_LOC_ACC	[CHAR (4)]
DIVISION_LOC_ACC	[CHAR (2)]
DIST_CHAN_LOC_ACC	[CHAR (2)]
DOC_NUMBER	[CHAR (10)]
ITM_NUMBER	[NUMC (6)]
LINEAR_UNIT	[UNIT (3)]
FIRST_OFFSET_TYPE_CODE	[CHAR (2)]
FIRST_OFFSET_UNIT	[UNIT (3)]
SECOND_OFFSET_TYPE_CODE	[CHAR (2)]
SECOND_OFFSET_UNIT	[UNIT (3)]
MARKER_DISTANCE_UNIT	[UNIT (3)]

EAMS_S_BO_NTF_HEADER-SUB_NUMBER = ANLA-ANLN2

ANLA
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]
ANLN2 [CHAR (4)]

EAMS_S_BO_NTF_HEADER-ASSET_NO = ANLH-ANLN1

ANLH
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]

EAMS_S_BO_NTF_HEADER-ORDERID = AUFK-AUFNR

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

EAMS_S_BO_NTF_HEADER-STDGORD = AUFK-AUFNR

CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

EAMS_S_BO_NTF_HEADER-STLMTORDER = AUFK-AUFNR

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

EAMS_S_BO_NTF_HEADER-PP_WKCTR = CRID-OBJID

EAML_D_OFFSET_TC
MANDT [CLNT (3)]
OFFSET_TC [CHAR (2)]

EAMS_S_BO_NTF_HEADER-COSTCENTER = CSKS-KOSTL

EQUI
MANDT [CLNT (3)]
EQUNR [CHAR (18)]

EAMS_S_BO_NTF_HEADER-FIRST_OFFSET_TYPE_CODE = EAML_D_OFFSET_TC-OFFSET_TC

IFLOT
MANDT [CLNT (3)]
TPLNR [CHAR (30)]

EAMS_S_BO_NTF_HEADER-EQUIPMENT = EQUI-EQUNR

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

EAMS_S_BO_NTF_HEADER-SECOND_OFFSET_TYPE_CODE = EAML_D_OFFSET_TC-OFFSET_TC

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

EAMS_S_BO_NTF_HEADER-EQUIPMENT = EQUI-EQUNR

MPLA
MANDT [CLNT (3)]
WARPL [CHAR (12)]

EAMS_S_BO_NTF_HEADER-FUNCT_LOC = IFLOT-TPLNR

MPOS
MANDT [CLNT (3)]
WAPOS [CHAR (16)]

EAMS_S_BO_NTF_HEADER-CUST_NO = KNA1-KUNNR

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

EAMS_S_BO_NTF_HEADER-ASSEMBLY = MARA-MATNR

QPCD
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]
CODEGRUPPE [CHAR (8)]
CODE [CHAR (4)]

EAMS_S_BO_NTF_HEADER-MATERIAL = MARA-MATNR

QGR
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]
CODEGRUPPE [CHAR (8)]

EAMS_S_BO_NTF_HEADER-MNTPLAN = MPLA-WARPL

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

EAMS_S_BO_NTF_HEADER-MAINTITEM = MPOS-WAPOS

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

EAMS_S_BO_NTF_HEADER-OBJECT NO = ONR00-OBJNR

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

EAMS_S_BO_NTF_HEADER-CODING = QPCD-CODE

T024I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
INGRP [CHAR (3)]

EAMS_S_BO_NTF_HEADER-CODE_GROUP = QGR-CODEGRUPPE

T352B
MANDT [CLNT (3)]
RBNR [CHAR (9)]

EAMS_S_BO_NTF_HEADER-COMP_CODE = T001-BUKRS

T356
MANDT [CLNT (3)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]

EAMS_S_BO_NTF_HEADER-MAINTPLANT = T001W-WERKS

T356A
MANDT [CLNT (3)]
ARTPR [CHAR (2)]

EAMS_S_BO_NTF_HEADER-FIRST_OFFSET_UNIT = T006-MSEHI

T357
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BEBER [CHAR (3)]

EAMS_S_BO_NTF_HEADER-LINEAR UNIT = T006-MSEHI

T370C
MANDT [CLNT (3)]
ABCKZ [CHAR (1)]

EAMS_S_BO_NTF_HEADER-MARKER_DISTANCE_UNIT = T006-MSEHI

T399I
MANDT [CLNT (3)]
IWERK [CHAR (4)]

EAMS_S_BO_NTF_HEADER-SECOND_OFFSET_UNIT = T006-MSEHI

T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

EAMS_S_BO_NTF_HEADER-UNIT = T006-MSEHI

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

EAMS_S_BO_NTF_HEADER-PLANGROUP = T024I-INGRP

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

EAMS_S_BO_NTF_HEADER-CATPROFILE = T352B-RBNR

TQ15
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]

EAMS_S_BO_NTF_HEADER-PRIORITY = T356-PRIOK

TQ80
MANDT [CLNT (3)]
QMART [CHAR (2)]

EAMS_S_BO_NTF_HEADER-PRIOTYPE = T356A-ARTPR

TSQA
MANDT [CLNT (3)]
SPART [CHAR (2)]

EAMS_S_BO_NTF_HEADER-PLSECTN = T357-BEBER

TTZZ
CLIENT [CLNT (3)]
TZONE [CHAR (6)]

EAMS_S_BO_NTF_HEADER-ABCINDIC = T370C-ABCKZ

TVBUR
MANDT [CLNT (3)]
VKBUR [CHAR (4)]

EAMS_S_BO_NTF_HEADER-PLANPLANT = T399I-IWERK

TVKGR
MANDT [CLNT (3)]
VKGRP [CHAR (3)]

EAMS_S_BO_NTF_HEADER-MAINTLOC = T499S-STAND

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]

EAMS_S_BO_NTF_HEADER-BUS_AREA = TGSB-GSBER

TVTWTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]

EAMS_S_BO_NTF_HEADER-CO_AREA = TKA01-KOKRS

VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]

EAMS_S_BO_NTF_HEADER-CAT_TYPE = TQ15-KATALOGART

VBUP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]

EAMS_S_BO_NTF_HEADER-NOTIF_TYPE = TQ80-QMART

EAMS_S_BO_NTF_HEADER-DIVISION = TSQA-SPART

EAMS_S_BO_NTF_HEADER-DIVISION_LOC_ACC = TSQA-SPART

EAMS_S_BO_NTF_HEADER-NOTIFTMEZ = TTZZ-TZONE

EAMS_S_BO_NTF_HEADER-SALES_OFFICE = TVBUR-VKBUR

EAMS_S_BO_NTF_HEADER-SALES_GRP = TVKGR-VKGRP

EAMS_S_BO_NTF_HEADER-SALES_ORG = TVKO-VKORG

EAMS_S_BO_NTF_HEADER-SALES_ORG_LOC_ACC = TVKO-VKORG

EAMS_S_BO_NTF_HEADER-DISTR_CHAN = TVTW-VTWEG

EAMS_S_BO_NTF_HEADER-DIST_CHAN_LOC_ACC = TVTW-VTWEG

EAMS_S_BO_NTF_HEADER-DOC_NUMBER = VBUK-VBELN

EAMS_S_BO_NTF_HEADER-SALES_ORD = VBUK-VBELN

EAMS_S_BO_NTF_HEADER-ITM_NUMBER = VBUP-POSNR