

SAP ABAP table EAMS_S_BO_TL_HEADER {Business Object Task List - Header Data}

EAMS_S_BO_TL_HEADER-AENNR = AENR-AENNR

AENR
MANDT [CLNT (3)]
AENNR [CHAR (12)]

EAMS_S_BO_TL_HEADER-NETID = CRID-OBJID

CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

EAMS_S_BO_TL_HEADER-SAFETY_CHAR = EAMWS_SAF_CHAR-SAFETY_CHAR

EAMWS_SAF_CHAR
MANDT [CLNT (3)]
SAFETY_CHAR [CHAR (1)]

EAMS_S_BO_TL_HEADER-ISTRU = MARA-MATNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

EAMS_S_BO_TL_HEADER-PSPNR = PRPSS-PSPNR

PRPSS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]

EAMS_S_BO_TL_HEADER-QDYNREGEL = QDDR-DYNREGEL

QDDR
MANDT [CLNT (3)]
DYNREGEL [CHAR (3)]

EAMS_S_BO_TL_HEADER-QPRZIEHVER = QPRVK-PRZIEHVERF

QPRVK
MANDT [CLNT (3)]
PRZIEHVERE [CHAR (8)]
VERSION [CHAR (6)]

EAMS_S_BO_TL_HEADER-MANDT = T000-MANDT

T000
MANDT [CLNT (3)]

EAMS_S_BO_TL_HEADER-QVEWERKS = T001W-WERKS

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

EAMS_S_BO_TL_HEADER-WERKS = T001W-WERKS

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

EAMS_S_BO_TL_HEADER-PLNME = T006-MSEHI

T024A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FEVOR [CHAR (3)]

EAMS_S_BO_TL_HEADER-VAGRP = T024A-FEVOR

EAMS_S_BO_TL_HEADER-STRAT = T351-STRAT

T351
MANDT [CLNT (3)]
STRAT [CHAR (6)]

EAMS_S_BO_TL_HEADER-ANLZU = T357M-ANLZU

T357M
MANDT [CLNT (3)]
ANLZU [CHAR (1)]

EAMS_S_BO_TL_HEADER-VERWE = T411-VERWE

T411
MANDT [CLNT (3)]
VERWE [CHAR (3)]

EAMS_S_BO_TL_HEADER-STATU = T412-PLNST

T412
MANDT [CLNT (3)]
PLNST [CHAR (3)]

EAMS_S_BO_TL_HEADER-PLNTY = TCA01-PLNTY

TCA01
MANDT [CLNT (3)]
PLNTY [CHAR (1)]

EAMS_S_BO_TL_HEADER-PROFIDNETZ = TCA41-PROFIDNETZ

TCA41
MANDT [CLNT (3)]
PLNAW [CHAR (1)]
PROFIDNETZ [CHAR (7)]

EAMS_S_BO_TL_HEADER-CCOAA = TCC13-CCOAA

TCC13
MANDT [CLNT (3)]
CCOAA [NUMC (3)]

EAMS_S_BO_TL_HEADER-KOKRS = TKA01-KOKRS

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

EAMS_S_BO_TL_HEADER-EXTNUM = TQ12-EXTNUM

TQ12
MANDT [CLNT (3)]
EXTNUM [CHAR (1)]

EAMS_S_BO_TL_HEADER-QDYNHEAD = TQ39A-DYNLEVEL

TQ39A
DYNLEVEL [CHAR (1)]

EAMS_S_BO_TL_HEADER-SLWBEZ = TQ79-SLWBEZ

TQ79
MANDT [CLNT (3)]
SLWBEZ [CHAR (3)]

EAMS_S_BO_TL_HEADER
MANDT [CLNT (3)]
PLNTY [CHAR (1)]
AENNR [CHAR (12)]
VERWE [CHAR (3)]
WERKS [CHAR (4)]
STATU [CHAR (3)]
PLNME [UNIT (3)]
VAGRP [CHAR (3)]
TXTSP [LANG (1)]
PROFIDNETZ [CHAR (7)]
KOKRS [CHAR (4)]
QVEWERKS [CHAR (4)]
QDYNREGEL [CHAR (3)]
QDYNHEAD [CHAR (1)]
QPRZIEHVER [CHAR (8)]
STRAT [CHAR (6)]
ISTRU [CHAR (18)]
ANLZU [CHAR (1)]
EXTNUM [CHAR (1)]
NETID [NUMC (8)]
PSPNR [NUMC (8)]
SLWBEZ [CHAR (3)]
CCOAA [NUMC (3)]
SAFETY_CHAR [CHAR (1)]

1 1 1 1 {0,1}

{0,1} {0,1} {0,1} 1