

HRPAYAT_PAYROLL_SIMU_PERNR
MASSN [CHAR (2)]
MASSG [CHAR (2)]
STAT1 [CHAR (1)]
STAT2 [CHAR (1)]
STAT3 [CHAR (1)]
BUKRS [CHAR (4)]
WERKS [CHAR (4)]
PERSG [CHAR (1)]
PERSK [CHAR (2)]
VDSK1 [CHAR (14)]
GSBER [CHAR (4)]
BTRTL [CHAR (4)]
ABKRS [CHAR (2)]
ANSVH [CHAR (2)]
KOSTL [CHAR (10)]
ORGEH [NUMC (8)]
PLANS [NUMC (8)]
STELL [NUMC (8)]
SACHA [CHAR (3)]
SACHP [CHAR (3)]
SACHZ [CHAR (3)]
OTYPE [CHAR (2)]
KOKRS [CHAR (4)]

HRPAYAT_PAYROLL_SIMU_PERNR-KOSTL = CSKS-KOSTL 0..N

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

HRPAYAT_PAYROLL_SIMU_PERNR-BUKRS = T001-BUKRS 0..N

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

HRPAYAT_PAYROLL_SIMU_PERNR-BTRTL = T001P-BTRTL 0..N

T001P
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BTRTL [CHAR (4)]

HRPAYAT_PAYROLL_SIMU_PERNR-WERKS = T500P-PERSA 0..N

T500P
MANDT [CLNT (3)]
PERSA [CHAR (4)]

HRPAYAT_PAYROLL_SIMU_PERNR-PERSG = T501-PERSG 0..N

T501
MANDT [CLNT (3)]
PERSG [CHAR (1)]

HRPAYAT_PAYROLL_SIMU_PERNR-PERSK = T503K-PERSK 0..N

T503K
MANDT [CLNT (3)]
PERSK [CHAR (2)]

HRPAYAT_PAYROLL_SIMU_PERNR-STELL = T513-STELL 0..N

T513
MANDT [CLNT (3)]
STELL [NUMC (8)]
ENDDA [DATS (8)]

HRPAYAT_PAYROLL_SIMU_PERNR-SACHA = T526-SACHX 0..N

T526
MANDT [CLNT (3)]
WERKS [CHAR (4)]
SACHX [CHAR (3)]

HRPAYAT_PAYROLL_SIMU_PERNR-SACHP = T526-SACHX 0..N

HRPAYAT_PAYROLL_SIMU_PERNR-SACHZ = T526-SACHX 0..N

T527O
MANDT [CLNT (3)]
HIRAR [CHAR (1)]
ORGKY [CHAR (14)]

HRPAYAT_PAYROLL_SIMU_PERNR-VDSK1 = T527O-ORGKY 0..N

HRPAYAT_PAYROLL_SIMU_PERNR-ORGEH = T527X-ORGEH 0..N

T527X
MANDT [CLNT (3)]
SPRSL [LANG (1)]
ORGEH [NUMC (8)]
ENDDA [DATS (8)]

HRPAYAT_PAYROLL_SIMU_PERNR-PLANS = T528B-PLANS 0..N

T528B
MANDT [CLNT (3)]
OTYPE [CHAR (2)]
PLANS [NUMC (8)]
ENDDA [DATS (8)]

HRPAYAT_PAYROLL_SIMU_PERNR-MASSN = T529A-MASSN 0..N

T529A
MANDT [CLNT (3)]
MASSN [CHAR (2)]

HRPAYAT_PAYROLL_SIMU_PERNR-STAT1 = T529U-STATV 0..N

T529U
MANDT [CLNT (3)]
SPRSL [LANG (1)]
STATN [NUMC (1)]
STATV [CHAR (1)]

HRPAYAT_PAYROLL_SIMU_PERNR-STAT2 = T529U-STATV 0..N

HRPAYAT_PAYROLL_SIMU_PERNR-STAT3 = T529U-STATV 0..N

HRPAYAT_PAYROLL_SIMU_PERNR-MASSG = T530-MASSG 0..N

T530
MANDT [CLNT (3)]
MASSN [CHAR (2)]
MASSG [CHAR (2)]

HRPAYAT_PAYROLL_SIMU_PERNR-ANSVH = T542A-ANSVH 0..N

T542A
MANDT [CLNT (3)]
MOLGA [CHAR (2)]
ANSVH [CHAR (2)]

HRPAYAT_PAYROLL_SIMU_PERNR-ABKRS = T549A-ABKRS 0..N

T549A
MANDT [CLNT (3)]
ABKRS [CHAR (2)]

HRPAYAT_PAYROLL_SIMU_PERNR-OTYPE = T778O-OTYPE 0..N

T778O
MANDT [CLNT (3)]
OTYPE [CHAR (2)]

HRPAYAT_PAYROLL_SIMU_PERNR-GSBER = TGSB-GSBER 0..N

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

HRPAYAT_PAYROLL_SIMU_PERNR-KOKRS = TKA01-KOKRS 0..N

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]