

SAP ABAP table HRV5550A {Generated Table for View}

HRV5550A
<u>MANDT</u> [CLNT (3)]
<u>PLVAR</u> [CHAR (2)]
<u>OTYPE</u> [CHAR (2)]
<u>OBJID</u> [NUMC (8)]
<u>SUBTY</u> [CHAR (4)]
<u>ISTAT</u> [CHAR (1)]
<u>BEGDA</u> [DATS (8)]
<u>ENDDA</u> [DATS (8)]
<u>TABSEQNR</u> [NUMC (6)]
<u>PATH_ID</u> [CHAR (30)]
<u>PARTNER_FUNCTION</u> [CHAR (8)]
<u>MAIN_POSITION</u> [CHAR (1)]
<u>DEFAULT_TERR</u> [CHAR (1)]
<u>DATA1</u> [CHAR (10)]
<u>DATA2</u> [CHAR (5)]
<u>FLAG1</u> [CHAR (1)]
<u>FLAG2</u> [CHAR (1)]

CRMM_V_TERR_ID
<u>CLIENT</u> [CLNT (3)]
<u>PATH_ID</u> [CHAR (30)]

PLOGI
<u>MANDT</u> [CLNT (3)]
<u>PLVAR</u> [CHAR (2)]
<u>OTYPE</u> [CHAR (2)]
<u>OBJID</u> [NUMC (8)]

T000
<u>MANDT</u> [CLNT (3)]

T778O
<u>MANDT</u> [CLNT (3)]
<u>OTYPE</u> [CHAR (2)]

T778P
<u>MANDT</u> [CLNT (3)]
<u>PLVAR</u> [CHAR (2)]

T778S
<u>MANDT</u> [CLNT (3)]
<u>ISTAT</u> [CHAR (1)]

HRV5550A-PATH_ID = CRMM_V_TERR_ID-PATH_ID 0..N

HRV5550A-OBJID = PLOGI-OBJID 0..N

HRV5550A-MANDT = T000-MANDT 0..N

HRV5550A-OTYPE = T778O-OTYPE

HRV5550A-PLVAR = T778P-PLVAR 0..N

HRV5550A-ISTAT = T778S-ISTAT 0..N