

SAP ABAP table HRVPADD2 {Generated Table for View HRVPADD2}

HRVPADD2
<u>MANDT</u> [CLNT (3)]
<u>PLVAR</u> [CHAR (2)]
<u>OTYPE</u> [CHAR (2)]
<u>OBJID</u> [NUMC (8)]
<u>RSIGN</u> [CHAR (1)]
<u>RELAT</u> [CHAR (3)]
<u>ISTAT</u> [CHAR (1)]
<u>PRIOX</u> [CHAR (2)]
<u>BEGDA</u> [DATS (8)]
<u>ENDDA</u> [DATS (8)]
<u>OTJID</u> [CHAR (10)]
<u>SUBTY</u> [CHAR (4)]
<u>SCLAS</u> [CHAR (2)]
<u>SOBID</u> [CHAR (45)]
<u>REPPR</u> [CHAR (12)]
<u>ACTIVE</u> [CHAR (1)]

PLOGI
<u>MANDT</u> [CLNT (3)]
<u>PLVAR</u> [CHAR (2)]
<u>OTYPE</u> [CHAR (2)]
<u>OBJID</u> [NUMC (8)]

T000
<u>MANDT</u> [CLNT (3)]

T778O
<u>MANDT</u> [CLNT (3)]
<u>OTYPE</u> [CHAR (2)]

T778P
<u>MANDT</u> [CLNT (3)]
<u>PLVAR</u> [CHAR (2)]

T778S
<u>MANDT</u> [CLNT (3)]
<u>ISTAT</u> [CHAR (1)]

T778V
<u>MANDT</u> [CLNT (3)]
<u>RELAT</u> [CHAR (3)]

T77RP
<u>MANDT</u> [CLNT (3)]
<u>REPPR</u> [CHAR (12)]

HRVPADD2-OBJID = PLOGI-OBJID 0..N

HRVPADD2-MANDT = T000-MANDT 0..N

HRVPADD2-OTYPE = T778O-OTYPE 0..N

HRVPADD2-SCLAS = T778O-OTYPE 0..N

HRVPADD2-PLVAR = T778P-PLVAR

HRVPADD2-ISTAT = T778S-ISTAT 0..N

HRVPADD2-RELAT = T778V-RELAT 0..N

HRVPADD2-REPPR = T77RP-REPPR 0..N