

SAP ABAP table JSTGEOHIE {IS-M/SD: Geographical Hierarchy}

JSTGEOHIE-AENDNRAB = JSTAENDER-AENDNR

JSTGEOHIE
<u>MANDT</u> [CLNT (3)]
<u>GEOEINUEB</u> [CHAR (10)]
<u>GEOEINUNT</u> [CHAR (10)]
<u>HTPGEO</u> [CHAR (2)]
<u>GUELTIGBIS</u> [DATS (8)]
<u>GUELTIGAB</u> [DATS (8)]
<u>AENDNRBIS</u> [CHAR (9)]
<u>AENDNRAB</u> [CHAR (9)]
<u>AENDNRINIT</u> [CHAR (9)]
<u>AENDNRAKT</u> [CHAR (9)]
<u>AENDNRVON</u> [CHAR (9)]
<u>AENDNRNACH</u> [CHAR (9)]

JSTAENDER
<u>MANDT</u> [CLNT (3)]
<u>AENDNR</u> [CHAR (9)]

JSTGEOEINH
<u>MANDT</u> [CLNT (3)]
<u>GEOEIN</u> [CHAR (10)]

T000
<u>MANDT</u> [CLNT (3)]

TJS01
<u>MANDT</u> [CLNT (3)]
<u>HTPGEO</u> [CHAR (2)]

0..N

JSTGEOHIE-AENDNRAKT = JSTAENDER-AENDNR

0..N

0..N

JSTGEOHIE-AENDNRBIS = JSTAENDER-AENDNR

0..N

0..N

JSTGEOHIE-AENDNRINIT = JSTAENDER-AENDNR

0..N

0..N

0..N

JSTGEOHIE-AENDNRNACH = JSTAENDER-AENDNR

0..N

0..N

0..N

JSTGEOHIE-AENDNRVON = JSTAENDER-AENDNR

0..N

1

JSTGEOHIE-GEOEINUEB = JSTGEOEINH-GEOEIN

1

JSTGEOHIE-GEOEINUNT = JSTGEOEINH-GEOEIN

0..N

0..N

1

JSTGEOHIE-MANDT = T000-MANDT

1

JSTGEOHIE-HTPGEO = TJS01-HTPGEO

0..N

0..N