

SAP ABAP table MGV_PKHD {Generated Table for View}

MGV_PKHD
MANDT [CLNT (3)]
PKNUM [CHAR (7)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
PRVBE [CHAR (10)]
VERID [CHAR (4)]
RGVER [CHAR (3)]
PKOSA [CHAR (12)]
PKSTE [CHAR (4)]
LGNUM [CHAR (3)]
LGTyp [CHAR (3)]
LGPLA [CHAR (10)]
PKSTF [CHAR (4)]
PKSTU [CHAR (4)]
LIFNR [CHAR (10)]
EKORG [CHAR (4)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
PKBHT [CHAR (18)]
UMLGO [CHAR (4)]
MEINS [UNIT (3)]
PKUMW [CHAR (4)]
PKSFG [CHAR (4)]
KCPRF [CHAR (4)]
VBELN [CHAR (10)]
PABPRF [CHAR (4)]

MGV_PKHD-PKOSA = AUFK-AUFNR 0..N	AUFK
	<u>MANDT</u> [CLNT (3)]
	<u>AUFNR</u> [CHAR (12)]

MGV_PKHD-PABPRF = CPABPRF-PABPRF	0..N
CPABPRF	
MANDT [CLNT (3)]	
PABPRF [CHAR (4)]	

MGV_PKHD-EBELN = EKKO-EBELN	0..N
EKKO	
<u>MANDT</u> [CLNT (3)]	
<u>EBELN</u> [CHAR (10)]	

MGV_PKHD-EBELP = EKPO-EBELP 	EKPO
	<u>MANDT</u> [CLNT (3)]
	<u>EBELN</u> [CHAR (10)]
	<u>EBELP</u> [NUMC (5)]

MGV_PKHD-LGPLA = LAGP-LGPLA	0..N	LAGP
		MANDT [CLNT (3)]
		<u>LGNUM</u> [CHAR (3)]
		<u>LGTyp</u> [CHAR (3)]
		<u>LGPLA</u> [CHAR (10)]

MGV_PKHD-LIFNR = LFA1-LIFNR	0..N
LFA1	
<u>MANDT</u> [CLNT (3)]	
<u>LIFNR</u> [CHAR (10)]	

MGV_PKHD-MATNR = MARA-MATNR	0..N
MARA	
<u>MANDT</u> [CLNT (3)]	
<u>MATNR</u> [CHAR (18)]	

MGV_PKHD-VERID = MKAL-VERID	MKAL
	<u>MANDT</u> [CLNT (3)]
	<u>MATNR</u> [CHAR (18)]
	<u>WERKS</u> [CHAR (4)]
	<u>VERID</u> [CHAR (4)]

MGV_PKHD-PRVBE = PVBE-PRVBE	0..N
PVBE	
<u>MANDT</u> [CLNT (3)]	
<u>WERKS</u> [CHAR (4)]	
<u>PRVBE</u> [CHAR (10)]	

MGV_PKHD-MANDT = T000-MANDT	0..N
	T000
	<u>MANDT</u> [CLNT (3)]

MGV_PKHD-UMLGO = T001L-LGORT	0..N	T001L
		MANDT [CLNT (3)]
		WERKS [CHAR (4)]
		LGORT [CHAR (4)]

MGV_PKHD-WERKS = T001W-WERKS	0..N	T001W
		<u>MANDT</u> [CLNT (3)]

MGV_PKHD-MEINS = T006-MSEHI	0..N
	<u>WERKS</u> [CHAR (4)]

MGV_PKHD-RGVER = T024D-DISPO	0..N	<u>MANDT</u> [CLNT (3)]
		<u>MSEHI</u> [UNIT (3)]

MGV_PKHD-EKORG = T024E-EKORG	0..N	<u>MANDT</u> [CLNT (3)]
		<u>WERKS</u> [CHAR (4)]
		<u>DISPO</u> [CHAR (3)]

MGV_PKHD-LGNUM = T300-LGNUM	0..N	T024E
		<u>MANDT</u> [CLNT (3)]
		<u>EKORG</u> [CHAR (4)]

MGV_PKHD-LGTYP = T301-LGTYP	0..N	T300
		MANDT [CLNT (3)]
		LGNUM [CHAR (3)]

MGV_PKHD-PKSTE = TPK01-PKSTE	0..N	TPK01
		MANDT [CLNT (3)]
		LGNUM [CHAR (3)]
		LGTYR [CHAR (3)]

MGV_PKHD-PKSTE = TPK02-PKSTE	0..N	TPK01
		MANDT [CLNT (3)]
		WERKS [CHAR (4)]
		PKSTU [CHAR (4)]

	PKSTF [CHAR (4)]
	TPK03

MGV_PKHD-KCPRF = TPKBP-KCPRF	0..N
	<u>WERKS</u> [CHAR (4)]
	PKSTU [CHAR (4)]

MGV_PKHD-PKSFG = TPKSF-PKSFG	0..N	<u>MANDT</u> [CLNT (3)]
		<u>WERKS</u> [CHAR (4)]
		<u>KCPRF</u> [CHAR (4)]

MGV_PKHD-VBELN = VBUK-VBELN	0..N
-----------------------------	------