

SAP ABAP table PLMW {MAPL-Dependent Charac. Specifications (Inspection Plan)}

| PLMW                          |
|-------------------------------|
| <u>MANDT</u> [CLNT (3)]       |
| <u>PLNTY</u> [CHAR (1)]       |
| <u>PLNNR</u> [CHAR (8)]       |
| <u>PLNKN</u> [NUMC (8)]       |
| <u>KZEINSTELL</u> [CHAR (1)]  |
| <u>MERKNR</u> [NUMC (4)]      |
| <u>ZUORDNR</u> [NUMC (4)]     |
| <u>ZAEHL</u> [NUMC (8)]       |
| <u>MATNR</u> [CHAR (18)]      |
| <u>TOLERANZSL</u> [CHAR (4)]  |
| <u>MASSEINHSW</u> [UNIT (3)]  |
| <u>KATALOGART1</u> [CHAR (1)] |
| <u>AUSWMGWRK1</u> [CHAR (4)]  |
| <u>KATALOGART2</u> [CHAR (1)] |
| <u>AUSWMGWRK2</u> [CHAR (4)]  |
| <u>KATALOGART3</u> [CHAR (1)] |
| <u>AUSWMGWRK3</u> [CHAR (4)]  |
| <u>KATALOGART4</u> [CHAR (1)] |
| <u>AUSWMGWRK4</u> [CHAR (4)]  |
| <u>KATALOGART5</u> [CHAR (1)] |
| <u>AUSWMGWRK5</u> [CHAR (4)]  |

PLMW-MATNR = MARA-MATNR

| MARA                     |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>MATNR</u> [CHAR (18)] |

PLMW-AUSWMGWRK1 = T001W-WERKS

PLMW-AUSWMGWRK2 = T001W-WERKS

PLMW-AUSWMGWRK3 = T001W-WERKS

PLMW-AUSWMGWRK4 = T001W-WERKS

PLMW-AUSWMGWRK5 = T001W-WERKS

PLMW-MASSEINHSW = T006-MSEHI

PLMW-KATALOGART1 = TQ15-KATALOGART

PLMW-KATALOGART2 = TQ15-KATALOGART

PLMW-KATALOGART3 = TQ15-KATALOGART

PLMW-KATALOGART4 = TQ15-KATALOGART

PLMW-KATALOGART5 = TQ15-KATALOGART

PLMW-TOLERANZSL = TQ29-TOLERANZSL

| T001W                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>WERKS</u> [CHAR (4)] |

| T006                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>MSEHI</u> [UNIT (3)] |

| TQ15                         |
|------------------------------|
| <u>MANDT</u> [CLNT (3)]      |
| <u>KATALOGART</u> [CHAR (2)] |

| TQ29                         |
|------------------------------|
| <u>MANDT</u> [CLNT (3)]      |
| <u>TOLERANZSL</u> [CHAR (4)] |