

# SAP ABAP table RELMC\_LM\_SETTINGS {General Settings in LUM (TIVLMSET)}

RELMC\_LM\_SETTINGS-LRDEFAULTAREA = T006-MSEHI

RELMC\_LM\_SETTINGS-NADEFAULTAREA = T006-MSEHI

RELMC\_LM\_SETTINGS-PLDEFAULTAREA = T006-MSEHI

RELMC\_LM\_SETTINGS-PLDEFAULTLENGTH = T006-MSEHI

RELMC\_LM\_SETTINGS-PLDEFAULTTIME = T006-MSEHI

RELMC\_LM\_SETTINGS-RCDEFAULTAREA = T006-MSEHI

RELMC\_LM\_SETTINGS-PECSVARNR = TBZ3-VARNR

RELMC\_LM\_SETTINGS-PEDPVARNR = TBZ3-VARNR

RELMC\_LM\_SETTINGS-PEERVARNR = TBZ3-VARNR

RELMC\_LM\_SETTINGS-PENHVARNR = TBZ3-VARNR

RELMC\_LM\_SETTINGS-PEPSVARNR = TBZ3-VARNR

RELMC\_LM\_SETTINGS-LRDEFAULTCURR = TCURC-WAERS

RELMC\_LM\_SETTINGS-NADEFAULTCURR = TCURC-WAERS

RELMC\_LM\_SETTINGS-PLDEFAULTLOCSYS = TIVBDLOCSYS-LOCSYS

RELMC\_LM\_SETTINGS-PLSLLOCSYS = TIVBDLOCSYS-LOCSYS

RELMC\_LM\_SETTINGS-PLCADASTRALMEAS = TIVBDMEAS-MEAS

RELMC\_LM\_SETTINGS-PLSLCUSAGETYPE = TIVLMPLSL-PLSLIDENO

RELMC_LM_SETTINGS
LRDEFAULTAREA [UNIT (3)]
LRDEFAULTCURR [CUKY (5)]
PLDEFAULTAREA [UNIT (3)]
PLDEFAULTLENGTH [UNIT (3)]
PLDEFAULTTIME [UNIT (3)]
PLDEFAULTLOCSYS [CHAR (4)]
PLCADASTRALMEAS [CHAR (4)]
PLSLLOCSYS [CHAR (4)]
PLSLCUSAGETYPE [CHAR (2)]
NADEFAULTAREA [UNIT (3)]
NADEFAULTCURR [CUKY (5)]
RCDEFAULTAREA [UNIT (3)]
PECSVARNR [CHAR (6)]
PENHVARNR [CHAR (6)]
PEPSVARNR [CHAR (6)]
PEDPVARNR [CHAR (6)]
PEERVARNR [CHAR (6)]

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

TBZ3
CLIENT [CLNT (3)]
OBJAP [CHAR (4)]
VARNR [CHAR (6)]

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

TIVBDLOCSYS
MANDT [CLNT (3)]
LOCSYS [CHAR (4)]

TIVBDMEAS
MANDT [CLNT (3)]
MEAS [CHAR (4)]

TIVLMPLSL
MANDT [CLNT (3)]
PLSLIDENO [CHAR (2)]

