

SAP ABAP table RJHAGAVB {IS-PAM: Update structure for JHAGA}

RJHAGAVB-DRERZ = JDTDRER-DRERZ

JDTDRER
<u>MANDT</u> [CLNT (3)]
DRERZ [CHAR (8)]

RJHAGAVB-PVA = JDTPVA-PVA

JDTPVA
<u>MANDT</u> [CLNT (3)]
<u>DRERZ</u> [CHAR (8)]
PVA [CHAR (8)]

RJHAGAVB-GPNR_RECH = JGTGPNR-GPNR

JGTGPNR
<u>MANDT</u> [CLNT (3)]
GPNR [CHAR (10)]

RJHAGAVB-REGULIERER = JGTGPNR-GPNR

JHAGA
<u>MANDT</u> [CLNT (3)]
<u>AVM_NR</u> [CHAR (10)]
<u>POS_NR</u> [NUMC (3)]
GRUPPABRNR [NUMC (3)]

RJHAGAVB-ZW_GRABRNR = JHAGA-GRUPPABRNR

JHAISZ
<u>MANDT</u> [CLNT (3)]
<u>AVM_NR</u> [CHAR (10)]
<u>POS_NR</u> [NUMC (3)]
<u>INSERTENT</u> [CHAR (10)]

RJHAGAVB-INSERTENT = JHAISZ-INSERTENT

RJHAGAVB-AVM_NR = JHAK-AVM_NR

JHAK
<u>MANDT</u> [CLNT (3)]
<u>AVM_NR</u> [CHAR (10)]

RJHAGAVB-MOTIV = JHAMOT-MOTIV

JHAMOT
<u>MANDT</u> [CLNT (3)]
<u>AVM_NR</u> [CHAR (10)]
MOTIV [NUMC (6)]

RJHAGAVB-POS_NR = JHAP-POS_NR

JHAP
<u>MANDT</u> [CLNT (3)]
<u>AVM_NR</u> [CHAR (10)]
<u>POS_NR</u> [NUMC (3)]

RJHAGAVB-REF_VBELN = JHTFK-VBELN

JHTFK
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]

RJHAGAVB-REF_POSNR = JHTFP-POSNR

JHTFP
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]
POSNR [NUMC (6)]

RJHAGAVB-ABSCHL_NR = JHTVABRUF-VTNR

JHTVABRUF
<u>MANDT</u> [CLNT (3)]
<u>VTNR</u> [NUMC (6)]
<u>POSNR</u> [NUMC (4)]
<u>AVM_NR</u> [CHAR (10)]
<u>POS_3NR</u> [NUMC (3)]
<u>GRUPPABRNR</u> [NUMC (3)]

RJHAGAVB-ABSCHL_NR2 = JHTVABRUF-VTNR

RJHAGAVB-ABSCHL_NR3 = JHTVABRUF-VTNR

RJHAGAVB-ABSCHL_PO2 = JHTVABRUF-POSNR

RJHAGAVB-ABSCHL_PO3 = JHTVABRUF-POSNR

RJHAGAVB-ABSCHL_POS = JHTVABRUF-POSNR

JHTVKO
<u>MANDT</u> [CLNT (3)]
<u>VTNR</u> [NUMC (6)]

RJHAGAVB-ACT_ABSCH2 = JHTVKO-VTNR

RJHAGAVB-ACT_ABSCH3 = JHTVKO-VTNR

RJHAGAVB-ACT_ABSCHL = JHTVKO-VTNR

JJTBE
<u>MANDT</u> [CLNT (3)]
BELEINH [CHAR (10)]

RJHAGAVB-BELEGEGINH = JJTBE-BELEINH

RJHAGAVB-UR_BELEINH = JJTBE-BELEINH

RJHAGAVB-IHKOMP = JJTIKO-INHALTSKOM

JJTIKO
<u>MANDT</u> [CLNT (3)]
<u>INHALTSKOM</u> [CHAR (8)]

RJHAGAVB-MANDT = T000-MANDT

T000
<u>MANDT</u> [CLNT (3)]

RJHAGAVB-KARENZ_ME = T006-MSEHI

T006
<u>MANDT</u> [CLNT (3)]
MSEHI [UNIT (3)]

RJHAGAVB-LAGME = T006-MSEHI

RJHAGAVB-SIGEW_ME = T006-MSEHI

T042Z
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]
ZLSCH [CHAR (1)]

RJHAGAVB-ZLSCH = T042Z-ZLSCH

RJHAGAVB-KDGRP = T151-KDGRP

T151
<u>MANDT</u> [CLNT (3)]
KDGRP [CHAR (2)]

RJHAGAVB-KONDA = T188-KONDA

T188
<u>MANDT</u> [CLNT (3)]
KONDA [CHAR (2)]

RJHAGAVB-PLTYP = T189-PLTYP

T189
<u>MANDT</u> [CLNT (3)]
PLTYP [CHAR (2)]

RJHAGAVB-AB_BR_WAEH = TCURC-WAERS

RJHAGAVB-WAERG = TCURC-WAERS

RJHAGAVB-KURST = TCURV-KURST

TCURV
<u>MANDT</u> [CLNT (3)]
KURST [CHAR (4)]

RJHAGAVB-PERFK = TFACD-IDENT

TFACD
<u>IDENT</u> [CHAR (2)]

RJHAGAVB-VAVARTYP = TJD05-VAVARTYP

TJD05
<u>MANDT</u> [CLNT (3)]
<u>VAVARTYP</u> [CHAR (2)]

RJHAGAVB-FKART = TJH05-FKART

TJH05
<u>MANDT</u> [CLNT (3)]
FKART [CHAR (4)]

RJHAGAVB-SI_TYP = TJH29-SI_TYP

TJH29
<u>MANDT</u> [CLNT (3)]
SI_TYP [CHAR (2)]

RJHAGAVB-TERM_TYP = TJH55-TERM_TYP

TJH55
<u>MANDT</u> [CLNT (3)]
TERM_TYP [CHAR (1)]

RJHAGAVB-BREITE_EH = TJH57-ISPEINHEIT

TJH57
<u>MANDT</u> [CLNT (3)]
<u>ISPEINHEIT</u> [UNIT (3)]

RJHAGAVB-ZUS_BERECH = TJH57-ISPEINHEIT

RJHAGAVB-HOEHE_EH = TJH61-ISPEINH_H

TJH61
<u>MANDT</u> [CLNT (3)]
<u>ISPEINH_H</u> [UNIT (3)]

RJHAGAVB-WERBK_TYP = TJH91-WKOMBI_TYP

TJH91
<u>MANDT</u> [CLNT (3)]
<u>WKOMBI_TYP</u> [CHAR (2)]

RJHAGAVB-PSTYV = TJHAP-PSTYV

TJHAP
<u>MANDT</u> [CLNT (3)]
PSTYV [CHAR (4)]

RJHAGAVB-SI_GEWKL = TJHGEWKL-SI_GEWKL

TJHGEWKL
<u>MANDT</u> [CLNT (3)]
<u>SI_GEWKL</u> [CHAR (4)]

RJHAGAVB-SI_SEKL = TJHSEKL-SI_SEKL

TJHSEKL
<u>MANDT</u> [CLNT (3)]
<u>SI_SEKL</u> [CHAR (4)]

RJHAGAVB-STORNOGRND = TJHSTOG-STORNOGRD

TJHSTOG
<u>MANDT</u> [CLNT (3)]
<u>STORNOGRD</u> [CHAR (3)]

RJHAGAVB-SEITE_FORM = TJJ01-SEITE_FORM

TJJ01
<u>MANDT</u> [CLNT (3)]
<u>SEITE_FORM</u> [CHAR (2)]

RJHAGAVB-AZART_FARB = TJJ11-AZART_FARB

TJJ11
<u>MANDT</u> [CLNT (3)]
<u>AZART_FARB</u> [CHAR (4)]

RJHAGAVB-AZART_AREA = TJJ13-AZART_AREA

TJJ13
<u>MANDT</u> [CLNT (3)]
<u>AZART_AREA</u> [CHAR (4)]

RJHAGAVB-AZART_FORM = TJJ17-AZART_FORM

TJJ17
<u>MANDT</u> [CLNT (3)]
<u>AZART_FORM</u> [CHAR (4)]

RJHAGAVB-AZART_GEST = TJJ19-AZART_GEST

TJJ19
<u>MANDT</u> [CLNT (3)]
<u>AZART_GEST</u> [CHAR (4)]

RJHAGAVB-SEITE_FSP = TJJ47-SEITE_FSP

TJJ47
<u>MANDT</u> [CLNT (3)]
<u>SEITE_FSP</u> [CHAR (4)]

RJHAGAVB-SFSP_ABR = TJJ47-SEITE_FSP

TJJ49
<u>MANDT</u> [CLNT (3)]
<u>AZART_SOND</u> [CHAR (2)]

RJHAGAVB-AZART_SOND = TJJ49-AZART_SOND

RJHAGAVB-PREIS_HTYT = TJJ51-IKO_HIETYP

TJJ51
<u>MANDT</u> [CLNT (3)]
<u>IKO_HIETYP</u> [CHAR (2)]

RJHAGAVB-STRUK_HTYT = TJJ51-IKO_HIETYP

RJHAGAVB-PREIS_HVAR = TJJ55-IKO_HIEVAR

TJJ55
<u>MANDT</u> [CLNT (3)]
<u>IKO_HIEVAR</u> [CHAR (6)]

RJHAGAVB-STRUK_HVAR = TJJ55-IKO_HIEVAR

RJHAGAVB-KUKARR_K = TJJ95-KUKARR

TJJ95
<u>MANDT</u> [CLNT (3)]
KUKARR [CHAR (2)]

RJHAGAVB-WS_TIMESLC = TJJW1-WS_TIMESLC

TJJW1
<u>MANDT</u> [CLNT (3)]
<u>WS_TIMESLC</u> [CHAR (2)]

RJHAGAVB-WS_BLOCK = TJJW3-WS_BLOCK

TJJW3
<u>MANDT</u> [CLNT (3)]
<u>WS_BLOCK</u> [CHAR (2)]

RJHAGAVB-STAFO = TMCB-STAFO

TMCB
<u>MANDT</u> [CLNT (3)]
<u>STAFO</u> [CHAR (6)]

RJHAGAVB-FAKSPP = TVFS-FAKSP

TVFS
<u>MANDT</u> [CLNT (3)]
<u>FAKSP</u> [CHAR (2)]

RJHAGAVB-KALKS = TVKD-KALKS

TVKD
<u>MANDT</u> [CLNT (3)]
KALKS [CHAR (1)]

RJHAGAVB
<u>MANDT</u> [CLNT (3)]
<u>AVM_NR</u> [CHAR (10)]
<u>POS_NR</u> [NUMC (3)]
<u>BELEGEINH</u> [CHAR (10)]
<u>UR_BELEINH</u> [CHAR (10)]
<u>INSERTENT</u> [CHAR (10)]
<u>REGULIERER</u> [CHAR (10)]
<u>GPNR_RECH</u> [CHAR (10)]
<u>MOTIV</u> [NUMC (6)]
<u>PSTYV</u> [CHAR (4)]
<u>AB_BR_WAEH</u> [CUKY (5)]
<u>FPRG_MEIN</u> [UNIT (3)]
<u>WAERG</u> [CUKY (5)]
<u>FAKSPP</u> [CHAR (2)]
<u>PERFK</u> [CHAR (2)]
<u>KONDA</u> [CHAR (2)]
<u>KALKS</u> [CHAR (1)]
<u>KUKARR_K</u> [CHAR (2)]
<u>KARENZ_ME</u> [UNIT (3)]
<u>KDGRP</u> [CHAR (2)]
<u>KURST</u> [CHAR (4)]
<u>PLTYP</u> [CHAR (2)]
<u>ZLSCH</u> [CHAR (1)]
<u>ACT_ABSCHL</u> [NUMC (6)]
<u>ABSCHL_NR</u> [NUMC (6)]
<u>ABSCHL_POS</u> [NUMC (4)]
<u>ACT_ABSCH2</u> [NUMC (6)]
<u>ABSCHL_NR2</u> [NUMC (6)]
<u>ABSCHL_PO2</u> [NUMC (4)]
<u>ACT_ABSCH3</u> [NUMC (6)]
<u>ABSCHL_NR3</u> [NUMC (6)]
<u>ABSCHL_PO3</u> [NUMC (4)]
<u>TERM_TYP</u> [CHAR (1)]
<u>VAVARTYP</u> [CHAR (2)]
<u>STRUK_HTYT</u> [CHAR (2)]
<u>STRUK_HVAR</u> [CHAR (6)]
<u>PREIS_HTYT</u> [CHAR (2)]
<u>PREIS_HVAR</u> [CHAR (6)]
<u>IHKOMP</u> [CHAR (8)]
<u>SEITE_FSP</u> [CHAR (4)]
<u>SEITE_FORM</u> [CHAR (2)]
<u>SFSP_ABR</u> [CHAR (4)]
<u>WERBK_TYP</u> [CHAR (2)]
<u>AZART_AREA</u> [CHAR (4)]
<u>BREITE_EH</u> [UNIT (3)]
<u>HOEHE_EH</u> [UNIT (3)]
<u>ZUS_BERECH</u> [UNIT (3)]
<u>AZART_GEST</u> [CHAR (4)]
<u>AZART_FORM</u> [CHAR (4)]
<u>AZART_FARB</u> [CHAR (4)]
<u>AZART_SOND</u> [CHAR (2)]
<u>FKART</u> [CHAR (4)]
<u>DRERZ</u> [CHAR (8)]
<u>PVA</u> [CHAR (8)]
<u>SI_TYP</u> [CHAR (2)]
<u>SIGEW_ME</u> [UNIT (3)]
<u>SI_GEWKL</u> [CHAR (4)]
<u>SI_SEKL</u> [CHAR (4)]
<u>WS_TIMESLC</u> [CHAR (2)]
<u>WS_BLOCK</u> [CHAR (2)]
<u>ZW_GRABRNR</u> [NUMC (3)]
<u>STORNOGRND</u> [CHAR (3)]
<u>REF_VBELN</u> [CHAR (10)]
<u>REF_POSNR</u> [NUMC (6)]
<u>STAFO</u> [CHAR (6)]