

SAP ABAP table RPLM_TS_QI_BAPI2045D4 {Inspection Result- Single-Value Level (with Tolerance Check)}

RPLM_TS_QI_BAPI2045D4
INSPLOT [NUMC (12)]
INSPSAMPLE [NUMC (6)]
ERR_CLASS [CHAR (2)]
CODE1 [CHAR (4)]
CODE2 [CHAR (4)]
CODE3 [CHAR (4)]
CODE4 [CHAR (4)]
CODE5 [CHAR (4)]

QALS
<u>MANDANT</u> [CLNT (3)]
<u>PRUEFLOS</u> [NUMC (12)]

QASV
<u>MANDANT</u> [CLNT (3)]
<u>PRUEFLOS</u> [NUMC (12)]
<u>VORGLFNR</u> [NUMC (8)]
<u>MERKNR</u> [NUMC (4)]
<u>PROBENR</u> [NUMC (6)]

QPCD
<u>MANDT</u> [CLNT (3)]
<u>KATALOGART</u> [CHAR (2)]
<u>CODEGRUPPE</u> [CHAR (8)]
<u>CODE</u> [CHAR (4)]

TQ17
<u>MANDT</u> [CLNT (3)]
<u>FEHLKLASSE</u> [CHAR (2)]

RPLM_TS_QI_BAPI2045D4-INSPLOT = QALS-PRUEFLOS 0..N

RPLM_TS_QI_BAPI2045D4-INSPSAMPLE = QASV-PROBENR 0..N

RPLM_TS_QI_BAPI2045D4-CODE1 = QPCD-CODE 0..N

RPLM_TS_QI_BAPI2045D4-CODE2 = QPCD-CODE 0..N

RPLM_TS_QI_BAPI2045D4-CODE3 = QPCD-CODE 0..N

RPLM_TS_QI_BAPI2045D4-CODE4 = QPCD-CODE 0..N

RPLM_TS_QI_BAPI2045D4-CODE5 = QPCD-CODE 0..N

RPLM_TS_QI_BAPI2045D4-ERR_CLASS = TQ17-FEHLKLASSE 0..N