

SAP ABAP table RPLM_TS_QI_INSPPOINT_LEVEL_INT {RPLM QI - Infos for Insp. Result - Inspection Point Level}

RPLM_TS_QI_INSPPOINT_LEVEL_INT
INSPLOT [NUMC (12)]
INSPSAMPLE [NUMC (6)]
ERR_CLASS [CHAR (2)]
RES_ORG [CHAR (2)]
CODE1 [CHAR (4)]
CODE2 [CHAR (4)]
CODE3 [CHAR (4)]
CODE4 [CHAR (4)]
CODE5 [CHAR (4)]

QALS
MANDANT [CLNT (3)]
PRUEFLOS [NUMC (12)]

QASV
MANDANT [CLNT (3)]
PRUEFLOS [NUMC (12)]
VORGLFNR [NUMC (8)]
MERKNR [NUMC (4)]
PROBENR [NUMC (6)]

QPCD
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]
CODEGRUPPE [CHAR (8)]
CODE [CHAR (4)]

TQ17
MANDT [CLNT (3)]
FEHLKLASSE [CHAR (2)]

TQ73
MANDT [CLNT (3)]
QERGDATH [CHAR (2)]

RPLM_TS_QI_INSPPOINT_LEVEL_INT-INSPLOT = QALS-PRUEFLOS

0..N

RPLM_TS_QI_INSPPOINT_LEVEL_INT-INSPSAMPLE = QASV-PROBENR

0..N

RPLM_TS_QI_INSPPOINT_LEVEL_INT-CODE1 = QPCD-CODE

0..N

RPLM_TS_QI_INSPPOINT_LEVEL_INT-CODE2 = QPCD-CODE

0..N

RPLM_TS_QI_INSPPOINT_LEVEL_INT-CODE3 = QPCD-CODE

0..N

RPLM_TS_QI_INSPPOINT_LEVEL_INT-CODE4 = QPCD-CODE

0..N

RPLM_TS_QI_INSPPOINT_LEVEL_INT-CODE5 = QPCD-CODE

0..N

RPLM_TS_QI_INSPPOINT_LEVEL_INT-ERR_CLASS = TQ17-FEHLKLASSE

0..N

RPLM_TS_QI_INSPPOINT_LEVEL_INT-RES_ORG = TQ73-QERGDATH

0..N

0..N