

SAP ABAP table RQMQMEL2 {General Notification - Header Data}

RQMQMEL2-/SAPSMOSS/ADDID = /SAPSMOSS/ADDID-R3ADDID

_SAPSMOSS_ADDID
MANDT [CLNT (3)]
R3ADDID [CHAR (10)]

RQMQMEL2-/SAPSMOSS/ADDREL = /SAPSMOSS/ADDRL-R3ADDREL

_SAPSMOSS_ADDRL
MANDT [CLNT (3)]
R3ADDREL [CHAR (10)]

RQMQMEL2-/SAPSMOSS/DBSYS = /SAPSMOSS/DBSY-DBSYS

_SAPSMOSS_DBSY
MANDT [CLNT (3)]
DBSYS [CHAR (10)]

RQMQMEL2-/SAPSMOSS/FRONT = /SAPSMOSS/FRNT-FRONTEND

_SAPSMOSS_FRNT
MANDT [CLNT (3)]
FRONTEND [CHAR (10)]

RQMQMEL2-/SAPSMOSS/INSTN = /SAPSMOSS/INSTN-R3INSTN

_SAPSMOSS_INSTN
MANDT [CLNT (3)]
R3INSTN [CHAR (10)]

RQMQMEL2-/SAPSMOSS/OSSYS = /SAPSMOSS/OSYS-OSSYS

_SAPSMOSS_OSYS
MANDT [CLNT (3)]
OSSYS [CHAR (10)]

RQMQMEL2-/SAPSMOSS/REL = /SAPSMOSS/REL-R3REL

_SAPSMOSS_REL
MANDT [CLNT (3)]
R3REL [CHAR (10)]

RQMQMEL2-/SAPSMOSS/STATUS = /SAPSMOSS/STAT-STATUS

_SAPSMOSS_STAT
STATUS [CHAR (1)]

RQMQMEL2-/SAPSMOSS/SYSTYP = /SAPSMOSS/SYST-R3SYSTYPE

_SAPSMOSS_SYST
MANDT [CLNT (3)]
R3SYSTYPE [CHAR (1)]

RQMQMEL2-AUFNR = AUFK-AUFNR

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

RQMQMEL2-COAFUNR = AUFK-AUFNR

CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

RQMQMEL2-FERTAUFNR = AUFK-AUFNR

RQMQMEL2-ARBPL = CRID-OBJID

RQMQMEL2-EBELN = EKKO-EBELN

EKKO
MANDT [CLNT (3)]
EBELN [CHAR (10)]

RQMQMEL2-EBELP = EKPO-EBELP

EKPO
MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]

RQMQMEL2-KUNUM = KNA1-KUNNR

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

RQMQMEL2-HERSTELLER = LFA1-LIFNR

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

RQMQMEL2-LIFNUM = LFA1-LIFNR

RQMQMEL2-EMATNR = MARA-MATNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

RQMQMEL2-MATNR = MARA-MATNR

RQMQMEL2-CHARG = MCH1-CHARG

MCH1
MANDT [CLNT (3)]
MATNR [CHAR (18)]
CHARG [CHAR (10)]

RQMQMEL2-RM_MATNR = MKAL-MATNR

MKAL
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
VERID [CHAR (4)]

RQMQMEL2-RM_WERKS = MKAL-WERKS

RQMQMEL2-VERID = MKAL-VERID

RQMQMEL2-OBJNR = ONR00-OBJNR

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

RQMQMEL2-OBJNR_REAL = ONR00-OBJNR

RQMQMEL2-OBJNR_STAT = ONR00-OBJNR

RQMQMEL2-PRUEFLOS = QALS-PRUEFLOS

QALS
MANDANT [CLNT (3)]
PRUEFLOS [NUMC (12)]

RQMQMEL2-QWRNUM = QMEL-QMNUM

QMEL
MANDT [CLNT (3)]
QMNUM [CHAR (12)]

RQMQMEL2-QMGRP = QPGR-CODEGRUPPE

QPGR
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]
CODEGRUPPE [CHAR (8)]

RQMQMEL2-SA_AUFNR = SAFK-AUFNR

SAFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

RQMQMEL2-MANDT = T000-MANDT

T000
MANDT [CLNT (3)]

RQMQMEL2-LGORTCHARG = T001L-LGORT

T001L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]

RQMQMEL2-LGORTVORG = T001L-LGORT

RQMQMEL2-ARBPLWERK = T001W-WERKS

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

RQMQMEL2-MAWERK = T001W-WERKS

RQMQMEL2-MGEIN = T006-MSEHI

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

RQMQMEL2-MATKL = T023-MATKL

T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]

RQMQMEL2-BKGRP = T024-EKGRP

T024
MANDT [CLNT (3)]
EKGRP [CHAR (3)]

RQMQMEL2-EKORG = T024E-EKORG

T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]

RQMQMEL2-PRDHA = T179-PRODH

T179
MANDT [CLNT (3)]
PRODH [CHAR (18)]

RQMQMEL2-RBNR = T352B-RBNR

T352B
MANDT [CLNT (3)]
RBNR [CHAR (9)]

RQMQMEL2-PRIOK = T356-PRIOK

T356
MANDT [CLNT (3)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]

RQMQMEL2-ARTPR = T356A-ARTPR

T356A
MANDT [CLNT (3)]
ARTPR [CHAR (2)]

RQMQMEL2-WAERS = TCURC-WAERS

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

RQMQMEL2-QMKAT = TQ15-KATALOGART

TQ15
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]

RQMQMEL2-QMART = TQ80-QMART

TQ80
MANDT [CLNT (3)]
QMART [CHAR (2)]

RQMQMEL2-AUSWIRK = TQ81-AUSWIRK

TQ81
MANDT [CLNT (3)]
AUSWIRK [CHAR (4)]

RQMQMEL2-TEILEV = TQ81V-TEILEV

TQ81V
MANDT [CLNT (3)]
TEILEV [CHAR (4)]

RQMQMEL2-FEART = TQ86-FEART

TQ86
MANDT [CLNT (3)]
FEART [CHAR (8)]

RQMQMEL2-SPART = TSPA-SPART

TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]

RQMQMEL2-TSEGTP = TTSEGTPLH-TEPL

TTSEGTPLH
CLIENT [CLNT (3)]
TEPL [CHAR (10)]

RQMQMEL2-TZONSO = TTZZ-TZONE

TTZZ
CLIENT [CLNT (3)]
TZONE [CHAR (6)]

RQMQMEL2-VKGRP = TVBVK-VKGRP

TVBVK
MANDT [CLNT (3)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]

RQMQMEL2-VKBUR = TVKBZ-VKBUR

TVKBZ
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
VKBUR [CHAR (4)]

RQMQMEL2-VKORG = TVKO-VKORG

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]

RQMQMEL2-VTWEG = TVTW-VTWEG

TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]

RQMQMEL2-LS_KDAUF = VBUK-VBELN

VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]

RQMQMEL2-LS_VBELN = VBUK-VBELN

RQMQMEL2-VBELN = VBUK-VBELN

VBUP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]

RQMQMEL2-LS_KDPOS = VBUP-POSNR

RQMQMEL2-LS_POSNR = VBUP-POSNR

RQMQMEL2
MANDT [CLNT (3)]
QMART [CHAR (2)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]
WAERS [CUKY (5)]
AUFNR [CHAR (12)]
VERID [CHAR (4)]
RM_MATNR [CHAR (18)]
RM_WERKS [CHAR (4)]
SA_AUFNR [CHAR (12)]
MATNR [CHAR (18)]
MATKL [CHAR (9)]
PRDHA [CHAR (18)]
KUNUM [CHAR (10)]
OBJNR [CHAR (22)]
RBNR [CHAR (9)]
LIFNUM [CHAR (10)]
VBELN [CHAR (10)]
SPART [CHAR (2)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
MAWERK [CHAR (4)]
QMKT [CHAR (1)]
QMGRP [CHAR (8)]
AUSWIRK [CHAR (4)]
TEILEV [CHAR (4)]
PRUEFLOS [NUMC (12)]
CHARG [CHAR (10)]
LGORTCHARG [CHAR (4)]
HERSTELLER [CHAR (10)]
EMATNR [CHAR (18)]
EKORG [CHAR (4)]
BKGRP [CHAR (3)]
LGORTVORG [CHAR (4)]
FERTAUFNR [CHAR (12)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
LS_KDAUF [CHAR (10)]
LS_KDPOS [NUMC (6)]
LS_VBELN [CHAR (10)]
LS_POSNR [NUMC (6)]
ARBPL [NUMC (8)]
ARBPLWERK [CHAR (4)]
FEART [CHAR (8)]
MGEIN [UNIT (3)]
COAFUNR [CHAR (12)]
QWRNUM [CHAR (12)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]
TSEGTP [CHAR (10)]
TZONSO [CHAR (6)]
_SAPSMOSS_INSTN [CHAR (10)]
_SAPSMOSS_OSSYS [CHAR (10)]
_SAPSMOSS_DBSYS [CHAR (10)]
_SAPSMOSS_REL [CHAR (10)]
_SAPSMOSS_FRONT [CHAR (10)]
_SAPSMOSS_SYSTYP [CHAR (1)]
_SAPSMOSS_ADDID [CHAR (10)]
_SAPSMOSS_ADDREL [CHAR (10)]
OBJNR_REAL [CHAR (22)]
OBJNR_STAT [CHAR (22)]

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N