

SAP ABAP table T7HK2B {Contribution plan attributes}

T7HK2B-MANDT = T000-MANDT

0..N

T000

MANDT [CLNT (3)]

T7HK2B-EEMWT = T512W-LGART

0..N

T512W

MANDT [CLNT (3)]

MOLGA [CHAR (2)]

LGART [CHAR (4)]

ENDDA [DATS (8)]

T7HK2B-EENWT = T512W-LGART

0..N

T7HK2B-ERMWT = T512W-LGART

0..N

T7HK2B-ERNWT = T512W-LGART

0..N

0..N

T54C2

MANDT [CLNT (3)]

CUMTY [CHAR (1)]

T7HK2B-SALWT = T512W-LGART

0..N

T7HK2B-CUMTY = T54C2-CUMTY

0..N

T7HK2B-CONTP = T7HK2-CONTP

T7HK2

MANDT [CLNT (3)]

CONTP [CHAR (4)]

T7HK2B-PLSTA = T7HK23-PLSTA

0..N

T7HK23

MANDT [CLNT (3)]

PLSTA [CHAR (2)]

T7HK2B-FTYPE = T7HK2G-FTYPE

0..N

T7HK2G

MANDT [CLNT (3)]

FTYPE [CHAR (4)]

T7HK2B-PROVR = T7HK2H-PROVR

0..N

T7HK2H

MANDT [CLNT (3)]

PROVR [CHAR (2)]

T7HK2B-SCALC = T7HK2P-SCALC

0..N

T7HK2P

MANDT [CLNT (3)]

SCALC [CHAR (2)]

0..N

T7HK2B

MANDT [CLNT (3)]

CONTP [CHAR (4)]

ENDDA [DATS (8)]

PROVR [CHAR (2)]

EEMWT [CHAR (4)]

EENWT [CHAR (4)]

ERMWT [CHAR (4)]

ERNWT [CHAR (4)]

SALWT [CHAR (4)]

SCALC [CHAR (2)]

FTYPE [CHAR (4)]

CUMTY [CHAR (1)]

PLSTA [CHAR (2)]

11