

SAP ABAP table TCACS_OTC03_OD {OTC 03 (Liability), Object-Specific Parameters}

TCACS_OTC03_OD-MANDT = T000-MANDT

T000
<u>MANDT</u> [CLNT (3)]

TCACS_APPLDEF
<u>APPL</u> [CHAR (6)]

TCACS_LOS_CONNEC
<u>OBJ_TYPE</u> [CHAR (2)]
<u>OBJ_METHOD</u> [CHAR (2)]
<u>TOOL</u> [CHAR (32)]
<u>TOOLFUNCTION</u> [CHAR (2)]

TCACS_LOS_OBJECT
<u>MANDT</u> [CLNT (3)]
<u>APPL</u> [CHAR (6)]
<u>OBJ_TYPE</u> [CHAR (2)]
<u>OBJ_ID</u> [CHAR (5)]
<u>VERSION</u> [NUMC (6)]

TCACS_VALSTAT1
<u>STATUSCLASS</u> [CHAR (1)]
<u>STATUS_VERSION</u> [CHAR (1)]
<u>STATUS_WORK</u> [CHAR (1)]

TCACS_OTC03_OD
<u>MANDT</u> [CLNT (3)]
<u>APPL</u> [CHAR (6)]
<u>OBJ_TYPE</u> [CHAR (2)]
<u>TOOL</u> [CHAR (32)]
<u>OBJ_ID</u> [CHAR (5)]
<u>VERSION</u> [NUMC (6)]
<u>STATUS_VERSION</u> [CHAR (1)]
<u>STATUS_WORK</u> [CHAR (1)]

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

1

0..N

0..N

0..N

0..N

TCACS_OTC03_OD-APPL = TCACS_APPLDEF-APPL

TCACS_OTC03_OD-OBJ_TYPE = TCACS_LOS_CONNEC-OBJ_TYPE

TCACS_OTC03_OD-TOOL = TCACS_LOS_CONNEC-TOOL

TCACS_OTC03_OD-OBJ_ID = TCACS_LOS_OBJECT-OBJ_ID

TCACS_OTC03_OD-STATUS_VERSION = TCACS_VALSTAT1-STATUS_VERSION {0,1}

TCACS_OTC03_OD-STATUS_WORK = TCACS_VALSTAT1-STATUS_WORK