

SAP ABAP table TISSR_UMS_DV {ISSR: Migration Stammdaten Umsetzung Kennzeichen DV}

TISSR_UMS_DV-MANDT = T000-MANDT

TISSR_UMS_DV
<u>MANDT</u> [CLNT (3)]
<u>COUNTRY_VAR</u> [CHAR (4)]
<u>DV_OLD</u> [CHAR (2)]
<u>DVUA_OLD</u> [CHAR (2)]
<u>ABS54AVAG_1</u> [CHAR (6)]
<u>ABS54AVAG_2</u> [CHAR (6)]
<u>EQ_ABS54A</u> [CHAR (1)]
<u>CHECK_BP</u> [CHAR (1)]
<u>BP_ENTITY_REP</u> [CHAR (2)]
<u>DV</u> [CHAR (5)]
<u>DVUA</u> [CHAR (2)]

T000
<u>MANDT</u> [CLNT (3)]

TISSR_ANLART
<u>MANDT</u> [CLNT (3)]
<u>COUNTRY_VAR</u> [CHAR (4)]
<u>ABS54AVAG</u> [CHAR (6)]

TISSR_DV
<u>MANDT</u> [CLNT (3)]
<u>COUNTRY_VAR</u> [CHAR (4)]
<u>DV</u> [CHAR (5)]

TISSR_DVUA
<u>MANDT</u> [CLNT (3)]
<u>COUNTRY_VAR</u> [CHAR (4)]
<u>DV</u> [CHAR (5)]
<u>DVUA</u> [CHAR (2)]

TISSR_MARECO
<u>MANDT</u> [CLNT (3)]
<u>COUNTRY_VAR</u> [CHAR (4)]

TZ30
<u>XLAND</u> [CHAR (2)]
<u>SANLF</u> [NUMC (3)]
<u>SDV</u> [CHAR (2)]

TZ31
<u>XLAND</u> [CHAR (2)]
<u>SANLF</u> [NUMC (3)]
<u>SDV</u> [CHAR (2)]
<u>SUABT</u> [CHAR (2)]

1

1

1

1

1

1

1

1

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

TISSR_UMS_DV-ABS54AVAG_1 = TISSR_ANLART-ABS54AVAG

TISSR_UMS_DV-ABS54AVAG_2 = TISSR_ANLART-ABS54AVAG

TISSR_UMS_DV-DV = TISSR_DV-DV

TISSR_UMS_DV-DVUA = TISSR_DVUA-DVUA

TISSR_UMS_DV-COUNTRY_VAR = TISSR_MARECO-COUNTRY_VAR

TISSR_UMS_DV-DV_OLD = TZ30-SDV

TISSR_UMS_DV-DVUA_OLD = TZ31-SUABT