

# SAP ABAP table U\_27800 {Generated Table for View}

U\_27800-MANDT = T000-MANDT

0..N

**T000**

MANDT [CLNT (3)]

U\_27800-SPRSL = T002-SPRAS

0..N

**T002**

SPRAS [LANG (1)]

U\_27800-MOLGA = T500L-MOLGA

0..N

**T500L**

MOLGA [CHAR (2)]

U\_27800-LGART = T512W-LGART

0..N

**T512W**

MANDT [CLNT (3)]

MOLGA [CHAR (2)]

LGART [CHAR (4)]

ENDDA [DATS (8)]

U\_27800-CPUNI = T538A-ZEINH

0..N

**T538A**

MANDT [CLNT (3)]

ZEINH [CHAR (3)]

U\_27800-CKPMO = T549R-PERMO

0..N

**T549R**

MANDT [CLNT (3)]

PERMO [NUMC (2)]

U\_27800-CPPMO = T549R-PERMO

0..N

U\_27800-CZTRT = T555A-ZTART

0..N

**T555A**

MANDT [CLNT (3)]

MOBDE [NUMC (2)]

ZTART [CHAR (4)]

ENDDA [DATS (8)]

U\_27800-ZASTO = T555A-ZTART

0..N

U\_27800-ZTART = T555A-ZTART

0..N

U\_27800-CMESS = T555E-ERROR

0..N

**T555E**

MANDT [CLNT (3)]

MOBDE [NUMC (2)]

ERRTY [CHAR (1)]

ERROR [CHAR (2)]

U\_27800-RMESS = T555E-ERROR

0..N

0..N

1,1

U_27800
<u>MANDT</u> [CLNT (3)]
<u>MOLGA</u> [CHAR (2)]
<u>MOBDE</u> [NUMC (2)]
<u>GRBAL</u> [CHAR (2)]
<u>BRULE</u> [NUMC (3)]
<u>ENDDA</u> [DATS (8)]
<u>SPRSL</u> [LANG (1)]
<u>CKPMO</u> [NUMC (2)]
<u>ZTART</u> [CHAR (4)]
<u>CPPMO</u> [NUMC (2)]
<u>CPUNI</u> [CHAR (3)]
<u>ZASTO</u> [CHAR (4)]
<u>CZTRT</u> [CHAR (4)]
<u>LGART</u> [CHAR (4)]
<u>CMESS</u> [CHAR (2)]
<u>RMESS</u> [CHAR (2)]

1

1

1

1

1

{0,1}

1

1

{0,1}

1

1