

SAP ABAP table V_AFABE_01 {Generated Table for View}

V_AFABE_01
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
AFABE [NUMC (2)]
WAERS [CUKY (5)]
RUNDEN [NUMC (1)]
ERWERT [CURR (13)]
GWGWRT [CURR (13)]
UMRWRT [CURR (13)]
GWGBST [CURR (13)]
FILLER [CHAR (1)]
RNDAHK [NUMC (1)]
ABGJA [NUMC (4)]
AFRHY [NUMC (3)]
XANZUM [CHAR (1)]
VERSN_011 [CHAR (4)]
X445R [CHAR (1)]
XAKPL [CHAR (1)]
BASRND [CHAR (1)]
METRND [CHAR (1)]
PERIV [CHAR (2)]
TOLERANZ [CURR (13)]
KZRBWB_AFABE [CHAR (1)]
AFAPL [CHAR (4)]
XSTORE [CHAR (1)]
ABVOR1 [CHAR (1)]
AFABE1 [NUMC (2)]
ANTEI1 [NUMC (1)]
ABVOR2 [CHAR (1)]
AFABE2 [NUMC (2)]
ANTEI2 [NUMC (1)]
ABVOR3 [CHAR (1)]
AFABE3 [NUMC (2)]
ANTEI3 [NUMC (1)]
ABVOR4 [CHAR (1)]
AFABE4 [NUMC (2)]
ANTEI4 [NUMC (1)]
VZANSW [CHAR (1)]
VZREST [CHAR (1)]
BUHBJT [CHAR (1)]
VIEW0 [NUMC (1)]
VIEW1 [NUMC (1)]
VIEW2 [NUMC (1)]
VIEW3 [NUMC (1)]
VIEW4 [NUMC (1)]
VIEW5 [NUMC (1)]
VIEW6 [NUMC (1)]
VZINVZ [CHAR (1)]
VZAWMA [CHAR (1)]
VZNAFA [CHAR (1)]
VZSAFA [CHAR (1)]
VZAAFA [CHAR (1)]
VZINDW [CHAR (1)]
VZZINS [CHAR (1)]
VZINDA [CHAR (1)]
AFABEQ [CHAR (1)]
XBEREP [CHAR (1)]
CORRBE [NUMC (2)]
GAFABER [CHAR (2)]
LDGRP_GL [CHAR (4)]
XAFABER [CHAR (1)]
ABWBER [NUMC (2)]
AREA_USAGE_IND [CHAR (1)]
WRTAFB [NUMC (2)]
PARAFB [NUMC (2)]
XINDHI [CHAR (1)]
XWRTID [CHAR (1)]
XINDID [CHAR (1)]
AFARFO [CHAR (4)]
XZUJHR [CHAR (1)]
XZUCOD [CHAR (1)]
XAFABH [CHAR (1)]
XUMHIS [CHAR (1)]
RVERS_GC [CHAR (3)]
HS1069 [CHAR (3)]
CURNO [NUMC (1)]
CURTP [CHAR (2)]
BERTYP [CHAR (2)]
VERSN [CHAR (3)]
XMENGE [CHAR (1)]

V_AFABE_01-LDGRP_GL = FAGL_TLDGRP-LDGRP

FAGL_TLDGRP
MANDT [CLNT (3)]
LDGRP [CHAR (4)]

V_AFABE_01-MANDT = T000-MANDT

T000
MANDT [CLNT (3)]

V_AFABE_01-BUKRS = T001-BUKRS

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

V_AFABE_01-PERIV = T009-PERIV

T009
MANDT [CLNT (3)]
PERIV [CHAR (2)]

V_AFABE_01-VERSN_011 = T011-VERSN

T011
MANDT [CLNT (3)]
VERSN [CHAR (4)]

V_AFABE_01-ABWBER = T093-AFABER

V_AFABE_01-AFABE = T093-AFABER

V_AFABE_01-AFABE1 = T093-AFABER

V_AFABE_01-AFABE2 = T093-AFABER

V_AFABE_01-AFABE3 = T093-AFABER

V_AFABE_01-AFABE4 = T093-AFABER

V_AFABE_01-CORRBE = T093-AFABER

V_AFABE_01-PARAFB = T093-AFABER

V_AFABE_01-WRTAFB = T093-AFABER

V_AFABE_01-GAFABER = T093G-GAFABER

V_AFABE_01-AFAPL = T096-AFAPL

V_AFABE_01-HS1069 = T852-RSUBD

V_AFABE_01-RVERS_GC = T858-RVERS

V_AFABE_01-WAERS = TCURC-WAERS

V_AFABE_01-VERSN = TKKAL-VERSA

T093
MANDT [CLNT (3)]
AFAPL [CHAR (4)]
AFABER [NUMC (2)]

T093G
MANDT [CLNT (3)]
GAFABER [CHAR (2)]

T096
MANDT [CLNT (3)]
AFAPL [CHAR (4)]

T852
MANDT [CLNT (3)]
RSUBD [CHAR (3)]

T858
MANDT [CLNT (3)]
RVERS [CHAR (3)]

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

TKKAL
MANDT [CLNT (3)]
AFAPL [CHAR (4)]
VERSA [CHAR (3)]