

SAP ABAP table V_EHAU_ADDRNR {Generated Table for View}

V_EHAU_ADDRNR
<u>MANDT</u> [CLNT (3)]
HAUS [CHAR (30)]
COUNC [CHAR (3)]
<u>REGIOGROUP</u> [CHAR (8)]
REGPOLIT [CHAR (8)]
REGIOGROUP_PERM [CHAR (8)]
<u>CRM_GUID</u> [RAW (16)]
<u>TPLNR</u> [CHAR (30)]
<u>MLANG</u> [LANG (1)]
<u>TPLKZ</u> [CHAR (5)]
<u>FLTYP</u> [CHAR (1)]
<u>TPLMA</u> [CHAR (30)]
<u>ERDAT</u> [DATS (8)]
<u>ERNAM</u> [CHAR (12)]
<u>AEDAT</u> [DATS (8)]
<u>AENAM</u> [CHAR (12)]
<u>DATAB</u> [DATS (8)]
<u>BEGRU</u> [CHAR (4)]
<u>TRPNR</u> [CHAR (30)]
<u>SUBMT</u> [CHAR (18)]
<u>SUBMTI</u> [CHAR (1)]
<u>IEQUI</u> [CHAR (1)]
<u>IEQUII</u> [CHAR (1)]
<u>EINZL</u> [CHAR (1)]
<u>EINZLI</u> [CHAR (1)]
<u>IWERK</u> [CHAR (4)]
<u>IWERKI</u> [CHAR (1)]
<u>INGRP</u> [CHAR (3)]
<u>INGRPI</u> [CHAR (1)]
<u>PM_OBJTY</u> [CHAR (2)]
<u>OBJNR</u> [CHAR (22)]
<u>POSNR</u> [CHAR (4)]
<u>ISTYP</u> [CHAR (1)]
<u>PREMS</u> [CHAR (10)]
<u>EQART</u> [CHAR (10)]
<u>INVNR</u> [CHAR (25)]
<u>GROES</u> [CHAR (18)]
<u>BRGEW</u> [QUAN (13)]
<u>GEWEI</u> [UNIT (3)]
<u>ANSWT</u> [CURR (13)]
<u>WAERS</u> [CUKY (5)]
<u>ANSDT</u> [DATS (8)]
<u>HERST</u> [CHAR (30)]
<u>HERLD</u> [CHAR (3)]
<u>BAUJJ</u> [CHAR (4)]
<u>BAUMM</u> [CHAR (2)]
<u>TYPBZ</u> [CHAR (20)]
<u>EMATN</u> [CHAR (18)]
<u>SERGE</u> [CHAR (30)]
<u>HANDLE</u> [CHAR (22)]
<u>TSEGTP</u> [CHAR (10)]
<u>FLLB_DUTY</u> [CHAR (1)]
<u>FLLB_HIDE</u> [CHAR (1)]
<u>IFLOT_SRTYPE</u> [CHAR (10)]
<u>IFLOT_SNTYPE</u> [CHAR (2)]
<u>ILOAN</u> [CHAR (12)]
ADDRNUMBER [CHAR (10)]
SWERK [CHAR (4)]

ADRC
<u>CLIENT</u> [CLNT (3)]
<u>ADDRNUMBER</u> [CHAR (10)]
<u>DATE_FROM</u> [DATS (8)]
<u>NATION</u> [CHAR (1)]

IFLOT
<u>MANDT</u> [CLNT (3)]
<u>TPLNR</u> [CHAR (30)]

IRLOT
<u>MANDT</u> [CLNT (3)]
<u>TRPNR</u> [CHAR (30)]

MARA
<u>MANDT</u> [CLNT (3)]
<u>MATNR</u> [CHAR (18)]

ONR00
<u>MANDT</u> [CLNT (3)]
<u>OBJNR</u> [CHAR (22)]

T000
<u>MANDT</u> [CLNT (3)]

T001W
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]

T002
<u>SPRAS</u> [LANG (1)]

T005
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

T024I
<u>MANDT</u> [CLNT (3)]
<u>IWERK</u> [CHAR (4)]
<u>INGRP</u> [CHAR (3)]

T370B
<u>MANDT</u> [CLNT (3)]
<u>BEGRU</u> [CHAR (4)]

T370F
<u>MANDT</u> [CLNT (3)]
<u>FLTYP</u> [CHAR (1)]

T370K
<u>MANDT</u> [CLNT (3)]
<u>EQART</u> [CHAR (10)]

T370S
<u>MANDT</u> [CLNT (3)]
<u>TPLKZ</u> [CHAR (5)]

T399I
<u>MANDT</u> [CLNT (3)]
<u>IWERK</u> [CHAR (4)]

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]

TQ80
<u>MANDT</u> [CLNT (3)]
<u>QMART</u> [CHAR (2)]

V_EHAU_ADDRNR-ADDRNUMBER = ADRC-ADDRNUMBER

0..N

V_EHAU_ADDRNR-HAUS = IFLOT-TPLNR

{0,1}

V_EHAU_ADDRNR-TPLMA = IFLOT-TPLNR

0..N

V_EHAU_ADDRNR-TRPNR = IRLOT-TRPNR

0..N

V_EHAU_ADDRNR-SUBMT = MARA-MATNR

0..N

V_EHAU_ADDRNR-OBJNR = ONR00-OBJNR

1

V_EHAU_ADDRNR-MANDT = T000-MANDT

0..N

V_EHAU_ADDRNR-SWERK = T001W-WERKS

0..N

V_EHAU_ADDRNR-MLANG = T002-SPRAS

0..N

V_EHAU_ADDRNR-HERLD = T005-LAND1

0..N

V_EHAU_ADDRNR-GEWEI = T006-MSEHI

V_EHAU_ADDRNR-INGRP = T024I-INGRP

0..N

V_EHAU_ADDRNR-BEGRU = T370B-BEGRU

0..N

V_EHAU_ADDRNR-FLTYP = T370F-FLTYP

0..N

V_EHAU_ADDRNR-EQART = T370K-EQART

0..N

V_EHAU_ADDRNR-TPLKZ = T370S-TPLKZ

0..N

V_EHAU_ADDRNR-IWERK = T399I-IWERK

0..N

V_EHAU_ADDRNR-WAERS = TCURC-WAERS

0..N

V_EHAU_ADDRNR-IFLOT_SNTYPE = TQ80-QMART

0..N