

SAP ABAP table V_FVKPG {Generated Table for View}

V_FVKPG
<u>CLIENT</u> [CLNT (3)]
DFVAL [CHAR (20)]
VKTYP [CHAR (2)]
VKONT [CHAR (12)]
GPART [CHAR (10)]
BEGRU [CHAR (4)]
ADDRNUMBER [CHAR (10)]
<u>NATION</u> [CHAR (1)]
MC_NAME1 [CHAR (35)]
MC_NAME2 [CHAR (35)]
CITY1 [CHAR (25)]
POST_CODE1 [CHAR (10)]
STREET [CHAR (25)]
HOUSE_NUM1 [CHAR (10)]
<u>COUNTRY</u> [CHAR (3)]
TEL_NUMBER [CHAR (30)]
TEL_EXTENS [CHAR (10)]
PO_BOX [CHAR (10)]
<u>RLTYP</u> [CHAR (6)]
AUGRP [CHAR (4)]

BUT000
<u>CLIENT</u> [CLNT (3)]
PARTNER [CHAR (10)]

FKKVK
<u>MANDT</u> [CLNT (3)]
<u>VKONT</u> [CHAR (12)]

T000
<u>MANDT</u> [CLNT (3)]

T005
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]

TB003
<u>CLIENT</u> [CLNT (3)]
<u>ROLE</u> [CHAR (6)]

TB037
<u>CLIENT</u> [CLNT (3)]
<u>AUOBJ</u> [CHAR (10)]
<u>AUGRP</u> [CHAR (4)]

TSADV
<u>NATION</u> [CHAR (1)]

V_FVKPG-GPART = BUT000-PARTNER 0..N

V_FVKPG-VKONT = FKKVK-VKONT 1..N

V_FVKPG-CLIENT = T000-MANDT 0..N

V_FVKPG-COUNTRY = T005-LAND1 0..N

V_FVKPG-RLTYP = TB003-ROLE

V_FVKPG-AUGRP = TB037-AUGRP 0..N

V_FVKPG-NATION = TSADV-NATION 0..N