

SAP ABAP table VIBRSCALES {Structure for scales for a condition type}

VIBRSCALES-SFORMREF = AT30-RFORMBEZ

0..N

AT30
RFORMBEZ [CHAR (4)]

VIBRSCALES-SBERFIMA = AT40-SBERFIMA

0..N

AT40
SBERFIMA [CHAR (4)]

VIBRSCALES-SPARTNR = BP000-PARTNR

0..N

BP000
MANDT [CLNT (3)]
PARTNR [CHAR (10)]

VIBRSCALES-KUNNR = KNA1-KUNNR

0..N

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

VIBRSCALES-MANDT = T000-MANDT

0..N

T000
MANDT [CLNT (3)]

VIBRSCALES-BUKRS = T001-BUKRS

0..N

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

VIBRSCALES-MWSKZ = T007A-MWSKZ

0..N

T007A
MANDT [CLNT (3)]
KALSM [CHAR (6)]
MWSKZ [CHAR (2)]

VIBRSCALES-ZAHLS = T008-ZAHLS

0..N

T008
MANDT [CLNT (3)]
ZAHLS [CHAR (1)]

VIBRSCALES-ZLSCH = T042Z-ZLSCH

0..N

T042Z
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
ZLSCH [CHAR (1)]

VIBRSCALES-MABER = T047M-MABER

0..N

T047M
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
MABER [CHAR (2)]

VIBRSCALES-SZSREF = T056R-REFERENZ

0..N

T056R
MANDT [CLNT (3)]
REFERENZ [CHAR (10)]

VIBRSCALES-SWHRKOND = TCURC-WAERS

0..N

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

VIBRSCALES-SZEGEN = TD21-SZEGEN

0..N

TD21
MANDT [CLNT (3)]
RANTYP [CHAR (1)]
SZEGEN [NUMC (2)]

VIBRSCALES-SZWKEY = TDZW-SZWKEY

0..N

TDZW
MANDT [CLNT (3)]
SZWKEY [CHAR (2)]

VIBRSCALES-SKALID = TFACD-IDENT

0..N

TFACD
IDENT [CHAR (2)]

VIBRSCALES-SKALID2 = TFACD-IDENT

0..N

TFACD
IDENT [CHAR (2)]

VIBRSCALES-SFLART = TIV08-SFLART

0..N

TIV08
MANDT [CLNT (3)]
SFLART [NUMC (4)]

VIBRSCALES-SANLF = TZAF-SANLF

0..N

TZAF
SANLF [NUMC (3)]

VIBRSCALES-SBEWZITI = TZB03-SBEWZITI

0..N

TZB03
SBEWZITI [CHAR (4)]

VIBRSCALES-SBUST = TZB09-SBUST

0..N

TZB09
RANTYP [CHAR (1)]
SBUST [NUMC (2)]

VIBRSCALES-SBEWHABEN = TZB0A-SBEWART

0..N

TZB0A
MANDT [CLNT (3)]
RANTYP [CHAR (1)]
SBEWART [CHAR (4)]

VIBRSCALES-SBEWSOLL = TZB0A-SBEWART

0..N

TZB0A
MANDT [CLNT (3)]
RANTYP [CHAR (1)]
SBEWART [CHAR (4)]

VIBRSCALES-SSTATI = TZC37-STATU

0..N

TZC37
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
GSART [CHAR (3)]
STATU [NUMC (2)]

VIBRSCALES-SBASIS = TZFB-SBASIS

0..N

TZFB
RANTYP [CHAR (1)]
SBASIS [CHAR (4)]

VIBRSCALES-SKOAREF = TZK01-SKOART

0..N

TZK01
MANDT [CLNT (3)]
RANTYP [CHAR (1)]
SKOART [NUMC (4)]

VIBRSCALES-SKOART = TZK01-SKOART

0..N

TZK01
MANDT [CLNT (3)]
RANTYP [CHAR (1)]
SKOART [NUMC (4)]

VIBRSCALES-SKOPO = TZK07-SKOPO

0..N

TZK07
MANDT [CLNT (3)]
RANTYP [CHAR (1)]
SKOART [NUMC (4)]
SKOPO [NUMC (2)]

1 1 1 1 0..N 1

VIBRSCALES
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
SANLF [NUMC (3)]
SKOART [NUMC (4)]
SSTATI [NUMC (2)]
SWHRKOND [CUKY (5)]
SBASIS [CHAR (4)]
SZSREF [CHAR (10)]
MWSKZ [CHAR (2)]
KUNNR [CHAR (10)]
ZLSCH [CHAR (1)]
MABER [CHAR (2)]
SPARTNR [CHAR (10)]
SKALID [CHAR (2)]
SZEGEN [NUMC (2)]
SBUST [NUMC (2)]
SKOPO [NUMC (2)]
SFORMREF [CHAR (4)]
SKALID2 [CHAR (2)]
SZWKEY [CHAR (2)]
SKOAREF [NUMC (4)]
SBEWSOLL [CHAR (4)]
SBEWHABEN [CHAR (4)]
SBEWZITI [CHAR (4)]
SBERFIMA [CHAR (4)]
ZAHLS [CHAR (1)]
SFLART [NUMC (4)]

1 1 1 1 1 1 1